

DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL

```
RRRRRRRR      PPPPPPPP      DDDDDDDD      CCCCCCCC      LL
RRRRRRRR      PPPPPPPP      DDDDDDDD      CCCCCCCC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RRRRRRRR      PPPPPPPP      DDDDDDDD      CCCCCCCC      LL
RRRRRRRR      PPPPPPPP      DDDDDDDD      CCCCCCCC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RR      RR      PP      PP      DD      DD      CC      LL
RR      RR      PP      PP      DDDDDDDD      CCCCCCCC      LL
RR      RR      PP      PP      DDDDDDDD      CCCCCCCC      LL
LLLLLLLLLLLL
```

```
LL      IIIIII      SSSSSSSS
LL      IIIIII      SSSSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SSSSSS
LL      II      SSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      IIIIII      SSSSSSSS
LLLLLLLLLLLL      IIIIII      SSSSSSSS
LLLLLLLLLLLL      IIIIII      SSSSSSSS
```


(2)	56	DECLARATIONS
(3)	83	RESULT PARSE INITIAL ENTRY
(4)	215	ENDPRM CALLBACK
(5)	294	INPUT(N), OUTPUT(N), GETQUAL CALLBACKS
(6)	410	ACTION CALLBACK SUBROUTINE
(7)	451	SCAN QUALIFIER DESCRIPTOR LIST
(8)	486	PROCESS AN INPUT/OUTPUT REQUEST
(9)	704	VALUE CONVERSION ROUTINES
(10)	800	PROCESS BIT LISTS
(11)	894	PROCESS ALL QUALIFIERS IN QUALIFIER LIST
(12)	953	PROCESS QUALIFIER
(13)	1002	RETURN EXPLICIT QUALIFIER VALUE
(14)	1055	RETURN QUALIFIER DEFAULT VALUE
(15)	1094	GET OPTION VALUE
(16)	1154	GET COMMAND LINE

```
0000 1      .TITLE RPDCL - RESULT PARSE MAIN ROUTINE
0000 2      .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6
0000 7 *
0000 8 *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 9 *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 10 *  ALL RIGHTS RESERVED.
0000 11 *
0000 12 *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 13 *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 14 *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 15 *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 16 *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 17 *  TRANSFERRED.
0000 18 *
0000 19 *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 20 *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 21 *  CORPORATION.
0000 22 *
0000 23 *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 24 *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 25 *
0000 26 *****
0000 27
0000 28
0000 29 ++
0000 30 ++ FACILITY:      STARLET DCL CLI
0000 31
0000 32 ++ ABSTRACT:      RESULT PARSE MAIN ROUTINE
0000 33
0000 34 ++ ENVIRONMENT:    NATIVE MODE USER CODE
0000 35
0000 36 ++ AUTHOR:         W.H.BROWN, CREATION DATE: 13-APR-77
0000 37
0000 38 ++ MODIFIED BY:
0000 39
0000 40 ++ V03-004 PCG0005      Peter George      30-Apr-1983
0000 41 ++          Change BSBW to JSB.
0000 42
0000 43 ++ V03-003 PCG0004      Peter George      15-Feb-1983
0000 44 ++          Convert to new structure level.
0000 45 ++          Reference qualifier number by PTR_B_NUMBER.
0000 46
0000 47 ++ V03-002 PCG0003      Peter George      15-Nov-1982
0000 48 ++          Use DCL$CNVNOEDIT instead of DCL$CNVNUMDEC.
0000 49 ++          Recognize NEXTQUAL callbacks.
0000 50
0000 51 ++ V03-001 PCG0002      Peter George      30-Sep-1982
0000 52 ++          Modify DCL$GETOPT to correctly check for syntax
0000 53 ++          changing entity. Refer to PTR length symbolically.
0000 54 ++
```



```

0000 56 .SBTTL DECLARATIONS
0000 57 :
0000 58 : MACRO LIBRARY CALLS
0000 59 :
0000 60 PRCDEF : DEFINE PROCESS WORK AREA
0000 61 WRKDEF : DEFINE COMMAND WORK AREA
0000 62 $$CLITABDEF : DEFINE TABLE STRUCTURES
0000 63 PTRDEF : DEFINE RESULT PARSE DESCRIPTOR FORMAT
0000 64 RPWDEF : RESULT PARSE WORK DEFINITIONS
0000 65 PLMDEF : PARAMETER LIMIT DEFINITIONS
0000 66 $CLIDF : CLI DEFINITIONS
0000 67 $CLIVERBDEF : VERB TYPE CODES
0000 68 $CLIMSGDEF : CLI MESSAGE DEFINITIONS
0000 69 :
0000 70 :
0000 71 : UTILITY CALL PARAMETER OFFSETS
0000 72 :
00000004 0000 73 RQDESC = 4 : OFFSET TO REQUEST DESCRIPTOR
00000008 0000 74 RQWORK = 8 : OFFSET TO WORK BLOCK
0000000C 0000 75 RQBITS = 12 : OFFSET TO BIT ARRAY ADDRESS
0000 76 :
0000 77 : INTERNAL ERROR BIT - DON'T USE R5 AS RESULT DESCRIPTOR INDEX
0000001F 0000 78 :
0000 79 :
0000 80 :
00000000 81 .PSECT DCL$ZCODE BYTE, RD, NOWRT

```

```
0000 83 .SBTTL RESULT PARSE INITIAL ENTRY
0000 84 :++
0000 85 FUNCTIONAL DESCRIPTION:
0000 86
0000 87 THIS IS THE ENTRY POINT USED FOR ALL UTILITY SERVICE
0000 88 CALL BACK REQUEST FOR SERVICE.
0000 89
0000 90 CALLING SEQUENCE:
0000 91
0000 92 CALL DCL$UTILSERV
0000 93
0000 94 INPUT PARAMETERS:
0000 95
0000 96 RQDESC(AP) IS THE ADDRESS OF THE REQUEST DESCRIPTOR
0000 97 RQWORK(AP) IS THE ADDRESS OF A WORK AREA FOR RESULT PARSE DATA
0000 98 RQBITS(AP) IS THE ADDRESS OF A BIT ARRAY FOR INPUT/OUTPUT
0000 99 PARAMETER DEFINITION REQUESTS
0000 100
0000 101 OUTPUT PARAMETERS:
0000 102
0000 103 THE FUNCTION IS PURFORMED, OR AN ERROR IS RETURNED
0000 104
0000 105 COMPLETION CODES:
0000 106
0000 107 RO = SUCCESS/FAILURE DEPENDING ON RESULT OF SEARCH
0000 108
0000 109 :--
0000 110 .ENTRY DCL$UTILSERV,^M<R2,R3,R4,R5,R6,R7,R8,R9,R10,R11>
0002 111
59 04 AC DO 0002 112 MOVL RQDESC(AP),R9 ; ADDRESS OF THE REQUEST DESCRIPTOR
04 04 ED 0006 113 CMPZV #CLISV_PRI1YP,#CLISS_PRI1YP,- ; THIS IS A REQUEST FOR A CLINT SERV
05 69 0009 114 CLISB_RQTYPE(R9),#CLISK_CLINT
03 12 000B 115 BNEQ 3$ ; BRANCH IF NO
00AA 31 000D 116 BRW CLINT
69 05 91 0010 117 3$: CMPB #CLISK_CLISERV,CLISB_RQTYPE(R9) ; THIS IS A REQUEST FOR A CLI SERVIC
05 12 0013 118 5$: BNEQ 5$ ; BR IF NO
01 A9 BE 0015 119 CHMS CLISW_SERVCOD(R9) ; THIS MUST BE DONE IN SUPER MODE
6F 11 0018 120 BRB RETO ; RETURN TO REQUESTOR
5A 08 AC DO 001A 121 5$: MOVL RQWORK(AP),R10 ; GET ADDRESS OF WORK AREA
001E 122 IFNORD #4,RPW_L_DCLWRK(R10),10$ ; CHECK IF WORK AREA IS ACCESSABLE
5B 04 AA DO 0025 123 MOVL RPW_L_DCLWRK(R10),R11 ; IF YES-GET THE WORK AREA
03 A9 94 0029 124 10$: CLRB CLISB_RQSTAT(R9) ; INITIAL RETURN STATUS FLAGS
08 A9 7C 002C 125 CLRQ CLISQ_RQDESC(R9) ; AND ZERO THE PARAMETER DESCRIPTOR
002F 126
002F 127 FROM THIS POINT ON, R5 MUST ALWAYS CONTAIN THE TOKEN DESCRIPTOR
002F 128 OF THE CURRENT TOKEN BEING PARSED SO THAT ERROR REPORTING WORKS.
002F 129
55 01 DO 002F 130 MOVL #1,R5 ; SET DEFAULT RESULT PARSE INDEX
8A'AF 6C FA 0032 131 CALLG (AP),B^RSLTPRS ; CALL FOR ERROR FRAME
00030000 8F C8 0036 132 BISL #<CLIS_ABKEYWB^XOFFF0000>,RO ; INCLUDE SUBSYSTEM NUMBER
49 50 E8 003D 133 BLBS RO,RETO ; BR IF NO ERRORS
0040 134
0040 135 CALL ERROR ACTION ROUTINE WITH ERROR. IF THE TOP BIT OF RO IS SET,
0040 136 THEN R2/R3 CONTAIN THE DESCRIPTOR OF THE TOKEN IN ERROR. IF R5 IS
0040 137 NON-ZERO, IT CONTAINS THE TOKEN INDEX OF THE TOKEN IN ERROR.
0040 138
21 50 1F E4 0040 139 CALERR: BBSC #INTERROR,RO,10$ ; BR IF THIS IS A INTERNAL ERROR
```



```

52 7C 0044 140 CLRQ R2 ; PRESET TOKEN DESCRIPTOR TO NULL
55 D5 0046 141 TSTL R5 ; IS TOKEN INDEX VALID?
1B 15 0048 142 BLEQ 10$ ; IF NOT, THEN RETURN NULL DESCRIPTOR
FFB3 30 004A 143 BSBW DCL$GETTEXTDESC ; TAKE APART DESCRIPTOR(POINT OF ERROR)
53 DD 004D 144 PUSHL R3 ; SAVE POINT OF ERROR
55 D6 004F 145 INCL R5 ; ADVANCE TO NEXT
FFAC 30 0051 146 BSBW DCL$GETTEXTDESC ; TAKE THAT APART
52 53 D0 0054 147 MOVL R3,R2 ; COPY ENDING ADDRESS OF ERROR
08 08 BA 0057 148 POPR #^M<R3> ; GET POINT OF ERROR BACK
52 53 C2 0059 149 SUBL R3,R2 ; FIND LENGTH OF ERROR SEGMENT
51 53 D7 005C 150 DECL R3 ; BACKUP TO PRECEEDING TERMINATOR
04 91 005E 151 CMPB #PTR_K_ENDLINE,R1 ; WAS ERROR AT END-OF-LINE?
02 12 0061 152 BNEQ 10$ ; BR IF NO-ALL IS CORRECT
52 D6 0063 153 INCL R2 ; ADJUST LENGTH FOR LAST LAST BYTE IN TOKEN
08 A9 52 7D 0065 154 10$: MOVQ R2,CLISQ RQDESC(R9) ; SET IN DESCRIPTOR
04 A9 DD 0069 155 PUSHL CLISA_ERRACT(R9) ; GET USER ERROR ROUTINE ADDRESS/OFFSET
1B 13 006C 156 BEQL RET0 ; BR IF NO ERROR ROUTINE
03 69 11 E0 006E 157 BBS #CLISV_ABSADR+<CLISB_RQFLGS*8>,(R9),20$ ; BR IF ADR IS ABSOLUTE
6E 59 C0 0072 158 ADDL R9,(SP) ; FIND REAL ADDRESS OF ROUTINE
5B 6A D0 0075 159 20$: MOVL (R10),R11 ; SET USER CONTEXT WORD
50 00030000 8F C8 007A 160 PUSHL R11 ; AND PASS IN ARGUMENT LIST
50 DD 0081 161 BISL #<CLIS_ABKEYW&^X0FFF0000>,R0 ; INCLUDE SUBSYSTEM NUMBER
59 DD 0083 162 PUSHL R0 ; ERROR CODE IS SECOND ARGUMENT INPUT
0C BE 03 FB 0085 163 PUSHL R9 ; REQUEST DESCRIPTOR IS FIRST ARGUMENT
04 0089 164 CALLS #3,012(SP) ; GIVE THE USER CHANCE TO HANDLE ERROR
04 008A 165 RET0: RET ; GO BACK FROM CALL BACK
04 008A 166
04 008A 167 ;
04 008A 168 ; RESULT PARSE DISPATCHER
04 008A 169 ;
04 008A 170
04 0000 008A 171 RSLTPRS: .WORD 0 ; REGISTERS ALREADY SAVED!
04 04 EF 008C 172 EXTZV #CLISV_PRITYP,#CLISS_PRITYP,- ; EXTRACT THE PRIMARY REQUEST
51 69 13 008F 173 CLISB_RQTYPE(R9),R1 ; FROM THE REQUEST DESCRIPTOR
04 00 EF 0091 174 BEQL 10$ ; BR IF REQUEST IS UTILITY TYPE
50 69 0093 175 EXTZV #CLISV_SUBTYP,#CLISS_SUBTYP,- ; GET THE PARAMETER NUMBER
0096 176 CLISB_RQTYPE(R9),R0 ; OR SUB TYPE FOR RESULT
0098 177 CASE R1,- ; DISPATCH ON REQUEST TYPE
0098 178 LIMIT=#CLISK_INPSPEC,<- ; STARTING WITH INPUT SPECIFICATION
0098 179 SETQUAL,- ; REQUEST FOR INPUT DEFINITION
0098 180 SETQUAL,- ; REQUEST FOR OUTPUT DEFINITION
0098 181 CMPPRM,- ; COMPLETED WITH PARAMETER SET
0098 182 DCL$VALCNV,- ; REQUEST FOR VALUE CONVERSION
0098 183 >
00A4 184 10$: CASE CLISB_RQTYPE(R9),- ; FALL THROUGH ON UTILITY OR ERROR
00A4 185 LIMIT=#CLISK_INITPRS,- ; DECODE UTILITY REQUEST
00A4 186 TYPE=B,<- ; LOW VALUE FOR CASE
00A4 187 DCL$RPINIT,- ; TYPE OF CASE IS BYTE
00A4 188 DCL$GETCMD,- ; INIT RESULT PARSE
00A4 189 SETQUAL,- ; GET COMMAND LINE DESCRIPTOR
00A4 190 DCL$GETOPT,- ; SET QUALIFER STATE
00A4 191 DCL$GETLINE+2,- ; GET COMMAND OPTION
00A4 192 DCL$GETLINE+2,- ; GET COMMAND LINE
00A4 193 > ; ** CLISERV SPACE HOLDER **
04 00B4 194 SETSTAT INVREQTYP ; INVALID REQUEST TYPE
04 00B9 195 RET ; DONE WITH THIS COMMAND

```

```

00BA 197
00BA 198 :
00BA 199 : NOTE WHEN DISPATCHING TO THESE BLISS ROUTINES, THE REGISTER MASK IS BEING
00BA 200 : SKIPPED OVER. THEREFORE, ALL REGISTERS MUST BE PUSHED BEFORE DISPATCHING.
00BA 201 :
00BA 202
00BA 203 CLINT: CASE CLISB RQTYPE(R9),- ; DECODE CLINT REQUEST
00BA 204 LIMIT=#CLISK_PRESENT,- ; LOW VALUE FOR CASE
00BA 205 TYPE=B,<- ; TYPE OF CASE IS BYTE
00BA 206 DCL$PRESENT+2,- ; DETERMINE IF ENTITY PRESENT
00BA 207 DCL$GETVALUE+2,- ; GET VALUE OF ENTITY
00BA 208 DCL$ENDPARSE+2,- ; CLEAN UP AFTER PARSING COMMAND LINE
00BA 209 DCL$DCLPARSE+2,- ; PARSE COMMAND LINE
00BA 210 DCL$DISPATCH+2,- ; DISPATCH TO ACTION ROUTINE
00BA 211 DCL$NEXTQUAL+2,- ; GET NEXT QUALIFIER
00BA 212 >
04 00CB 213 RET ; DONE WITH THIS COMMAND

```



```
00CC 215 .SBTTL ENDPRM CALLBACK
00CC 216 :---
00CC 217 :
00CC 218 : FUNCTIONAL DESCRIPTION:
00CC 219 :
00CC 220 : THIS ROUTINE IS CALLED WHEN ALL QUALIFIERS AND
00CC 221 : VALUES HAVE BEEN RETRIEVED FOR A GIVEN PARAMETER.
00CC 222 : A CHECK IS MADE TO ENSURE THAT ALL QUALIFIERS
00CC 223 : PRESENT ON THE COMMAND LINE HAVE BEEN PROCESSED
00CC 224 : BY THE UTILITY.
00CC 225 :
00CC 226 : INPUTS:
00CC 227 :
00CC 228 : R0 = PARAMETER NUMBER TO BE TERMINATED
00CC 229 : R9 = ADDRESS OF REQUEST DESCRIPTOR BLOCK
00CC 230 : R10 = ADDRESS OF IMAGE LOCAL WORK AREA
00CC 231 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
00CC 232 :
00CC 233 : OUTPUTS:
00CC 234 :
00CC 235 : THE REQUEST IS PROCESSED.
00CC 236 :---
00CC 237 CMPPRM:
56 40 AA40 DE 00CC 238 MOVAL RPW_G_PRMLIM(R10)[R0],R6 ; SET ADDRESS OF PROPER LIMIT DESC
7E 01 7D 00D1 239 MOVQ #1,=(SP) ; SET SUCCESS PLUS A ZERO LONG WORD
58 5E D0 00D4 240 MOVL SP,R8 ; MARK POINT OF ERROR PARAMETERS
00D7 241 ; NOTE: R5 WAS ZEROED IN INITIAL ENTRY
08 AA 55 91 00D7 242 10$: CMPB R5,RPW_B_STRPARAM(R10) ; IS INDEX AT END COMD QUALIFIER AREA?
06 12 00DB 243 BNEQ 20$ ; BR IF NO
55 01 A6 9A 00DD 244 MOVZBL PLM_B_FSTDESC(R6),R5 ; ELSE SET START OF PARAMETER AREA
60 13 00E1 245 BEQL 80$ ; BR IF PARAMETER IS NON-EXISTANT
02 A6 55 91 00E3 246 20$: CMPB R5,PLM_B_LSTDESC(R6) ; IS INDEX OUT OF CURRENT PARAMETER?
1A 1A 00E7 247 BGTRU 50$ ; BR IF ALL DONE
FF14' 30 00E9 248 BSBW DCL$GETTEXTDESC ; GET AND EXTRACT DESCRIPTOR
00EC 249 ASSUME PTR_K_PARMQUAL EQ 1
00EC 250 ASSUME PTR_K_COMDQUAL EQ 0
01 51 91 00EC 251 CMPB R1,#PTR_K_PARMQUAL ; ANY KIND OF QUALIFIER?
0E 1A 00EF 252 BGTRU 40$ ; IF NO BR AND CONTINUE SEARCH
09 20 AA 55 E0 00F1 253 BBS R5,RPW_G_BITS(R10),40$ ; BR IF THE QUALIFIER HAS BEEN SEEN
00F6 254 SETSTAT UNPROQAL
46'AF 6C FA 00FB 255 CALLG (AP),B*100$ ; PROCESS ERROR CALL BACK
55 D6 00FF 256 40$: INCL R5 ; ADD 1 TO BUFFER INDEX
D4 11 0101 257 BRB 10$ ; KEEP LOOKING
55 66 9A 0103 258 50$: MOVZBL PLM_B_NXTDESC(R6),R5 ; NEXT DESCRIPTOR TO PROCESS
3B 13 0106 259 BEQL 80$ ; BR IF NO PARAMETER PRESENT
02 A6 55 91 0108 260 CMPB R5,PLM_B_LSTDESC(R6) ; ALL BEEN PROCESSED
09 1A 010C 261 BGTRU 55$ ; BR IF YES
010E 262 SETSTAT UNPROPARM ; UNPROCESSED PARAMETERS
46'AF 6C FA 0113 263 CALLG (AP),B*100$ ; GENERATE AN ERROR
55 02 A6 9A 0117 264 55$: MOVZBL PLM_B_LSTDESC(R6),R5 ; INDEX TO LAST DESCRIPTOR
55 96 011B 265 INCB R5 ; SET TO NEXT DESCRIPTOR INDEX
03 A6 55 91 011D 266 CMPB R5,PLM_B_TRMDESC(R6) ; IS THIS THE TERMINATOR DESCRIPTOR?
20 1E 0121 267 BGEQU 80$ ; BR IF YES-NOTHING MORE TO DO!
66 55 90 0123 268 MOVB R5,PLM_B_NXTDESC(R6) ; SET THAT AS NEXT FOR NEXT CALLBACK
FED7' 30 0126 269 60$: BSBW DCL$GETPARM ; FIND THE NEXT PARAMETER
0A 50 E9 0129 270 BLBC R0,70$ ; BR IF NONE REMAIN
01 53 91 012C 271 CMPB R3,#PTR_K_BLANK ; CHECK IF END OF PARAMETER LIST
```

```

02 A6 05 05 13 012F 272 BEQL 70$ : BR IF YES-SET NEW LIMIT TO HERE
      53 91 0131 273 CMPB R3,#PTR_K_COMMA : HOW ABOUT LIST SEPARATOR?
      F0 12 0134 274 BNEQ 60$ : KEEP LOOKING
      55 01 83 0136 275 70$: SUBB3 #1,R5,PLM_B_LSTDESC(R6) : SET NEW LAST
      04 88 013B 276 BISB #CLISM_MOREINP,- : SET FLAG THAT MORE INPUT EXISTS
      03 A9 013D 277 CLISB_RQSTAT(R9) : INDICATE MORE DATA TO COME
      66 90 013F 278 MOVB PLM_B_NXTDESC(R6),- : SET PREVIOUS NEXT AS
      01 A6 0141 279 PLM_B_FSTDESC(R6) : AS FIRST IN THIS PARAMETER
      21 BA 0143 280 80$: POPR : GET STATUS AND POINT OF ERROR(IF ONE)
      04 04 0145 281 90$: RET
      0146 282 :
      0146 283 : THIS ROUTINE IS CALLED TO FACILITATE MULTIPLE ERROR
      0146 284 : ACTION CALLS WHEN PROCESSING THE END OF A PARAMETER SET
      0146 285 :
      0820 0146 286 100$: .WORD ^M<R5,R11> : SAVE REGISTERS 5 AND 11
      21 BB 0148 287 PUSHR #^M<R0,R5> : SET ERROR AND PLACE IN THE LINE
      50 68 D0 014A 288 MOVL (R8),R0 : GET PRVIOUS ERROR
      55 04 A8 D0 014D 289 MOVL 4(R8),R5 : GET PREVIOUS PLACE
      68 8E 7D 0151 290 MOVQ (SP)+,(R8) : SET THE NEW AS NEXT TO DO
      EE 50 E8 0154 291 BLBS R0,90$ : BR IF FIRST TIME THROUGH
      FEE6 31 0157 292 BRW CALERR : GO CALL THE UTILITY WITH ERROR

```



```
015A 294 .SBTTL INPUT(N),OUTPUT(N),GETQUAL CALLBACKS
015A 295 ---
015A 296 :
015A 297 : FUNCTIONAL DESCRIPTION:
015A 298 :
015A 299 : THIS ROUTINE HANDLES THE INPUT, OUTPUT AND GETQUAL
015A 300 : CALLBACKS TO SUPPLY AN INPUT/OUTPUT PARAMETER OR
015A 301 : PROCESS ALL QUALIFIERS ASSOCIATED WITH A GIVEN
015A 302 : PARAMETER OR VERB.
015A 303 :
015A 304 : INPUTS:
015A 305 :
015A 306 : R0 = INPUT OR OUTPUT NUMBER (IF INPUT/OUTPUT REQUEST)
015A 307 : R9 = ADDRESS OF REQUEST DESCRIPTOR BLOCK
015A 308 : R10 = ADDRESS OF IMAGE LOCAL WORK AREA
015A 309 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
015A 310 :
015A 311 : OUTPUTS:
015A 312 :
015A 313 : THE REQUEST IS PROCESSED.
015A 314 : ---
015A 315 : SETQUAL:
58 0C AC DO 015A 316 : MOVL RQBITS(AP),R8 ; GET USERS BIT ARRAY
015E 317 :
015E 318 : RESET ALL STATUS FLAGS AND DESCRIPTORS FOR ALL QUALIFIER BLOCKS
015E 319 : LINKED TO THE CALLING REQUEST DESCRIPTOR BLOCK
015E 320 :
0244'CF DF 015E 321 : PUSHAL W^SCANQUAL ; SET INITIAL ADDRESS FOR QUALIFER SCAN
0162 322 10$: JSB @ (SP)+ ; CO-ROUTINE LINK TO SCAN QUALIFIERS
08 50 E9 0164 323 : BLBC R0,20$ ; BR WHEN ALL ARE SCANNED
03 A7 94 0167 324 : CLRB CLISB_QDSTAT(R7) ; RESET ALL STATUS FLAGS
04 A7 7C 016A 325 : CLRQ CLISQ_QDVALDESC(R7) ; SET VALUE DESCRIPTOR TO ZERO
F3 11 016D 326 : BRB 10$ ; TRY FOR NEXT
016F 327 :
016F 328 : IF GETQUAL REQUEST, THEN FOR EACH QUALIFIER DESCRIPTOR BLOCK LINKED
016F 329 : TO THIS REQUEST DESCRIPTOR, PROCESS THE COMMAND QUALIFIER (IF PRESENT).
016F 330 :
02 69 91 016F 331 20$: CMPB CLISB_RQTYPE(R9),#CLISK_GETQUAL ; IS THIS REQUEST FOR QUALIFER
0172 332 : BNEQ 25$ ; DEFINITION ONLY- BR IF NO
C2 AB 90 0174 333 : MOVB WRK_B_VERBTYP(R11),- ; SET COMMAND GENERIC VERB TYPE INTO
03 A9 0177 334 : CLISB_RQSTAT(R9) ; REQUEST DESCRIPTOR STATUS BYTE
038E 30 0179 335 : BSBW DCLSPROCMDQUAL ; FIND COMMAND QUALIFIER
24 11 017C 336 : BRB 40$ ; TAKE ACTION
017E 337 :
017E 338 : IF INPUT(N) OR OUTPUT(N) REQUEST, THEN FIND THE PARAMETER OR QUALIFIER
017E 339 : DESCRIBING THE INPUT OR OUTPUT AND PROCESS IT.
017E 340 :
00E7 30 017E 341 25$: BSBW PROCIO ; PROCESS INPUT/OUTPUT DESCRIPTION
52 01 A9 9A 0181 342 : MOVZBL CLISB_BITNUM(R9),R2 ; GET THE PARAMETER PRESENT FLAG BIT
00 E0 0185 343 : BBS #CLISV_PARMPRS,- ; BR IF THE PARAMETER IS PRESENT
14 03 A9 0187 344 : CLISB_RQSTAT(R9),30$ ;
018A 345 : CLRBIT R2,(R8) ; INDICATE PARAMETER ABSENT
018E 346 : SETSTAT REQPRMABS ; SET REQUIRED PARAMETER ABSENT
BBS 347 : #CLISV_PARMREQ,- ; BR IF PARAMETER IS REQUIRED
75 02 A9 E0 0193 348 : CLISB_RQFLGS(R9),140$ ;
51 14 A9 DO 0198 349 : MOVL CLISA_ABSACT(R9),R1 ; GET PARAMETER ABSENT ACTION ADDRESS
65 11 019C 350 : BRB 120$ ; JOIN COMMON ROUTINE
```



```
019E 351 30$: SETBIT R2,(R8) ; SET PARAMETER PRESENT FLAG
01A2 352
01A2 353 INITIALIZE 4 COROUTINE START ADDRESSES FOR THE FOLLOWING
01A2 354 4 PASSES THROUGH ALL OF THE QUALIFIER DESCRIPTOR BLOCKS LINKED
01A2 355 TO THE REQUEST DESCRIPTOR.
01A2 356
0244'CF 9F 01A2 357 40$: PUSHAB W^SCANQUAL ; SET INITIAL COROUTINE ADDRESS
6E DD 01A6 358 PUSHL (SP) ; COPY COROUTINE INITIAL ADDRESS
6E DD 01A8 359 PUSHL (SP) ; THREE MORE TIMES FOR
6E DD 01AA 360 PUSHL (SP) ; SUBSEQUENT SCANS OF QUALIFIERS
01AC 361
01AC 362 MARK ALL QUALIFIERS WITH DEFTRUE AS BEING PRESENT
01AC 363
01AC 364 45$: JSB @ (SP)+ ; GET NEXT QUALIFIER DESCRIPTOR
1A 50 E9 01AE 365 BLBC R0,50$ ; BR WHEN SCAN IS DONE
F6 03 A7 01 E0 01B1 366 BBS #CLISV_QUALEXP,CLISB_QDSTAT(R7),45$ ; LOOP IF FOUND EXPLICITLY
51 01 A7 9A 01B6 367 MOVZBL CLISB_QDCODE(R7),R1 ; GET THE INDEX INTO THE TABLE
FE43' 30 01BA 368 BSBW DCL$GETPARMQUAL ; FIND THE ASSOCIATED STRUCTURE
EA 04 A2 02 E1 01BD 369 BBC #ENT V_DEFTRUE,ENT W_FLAGS(R2),45$ ; BR IF NOT DEFAULTED TRUE
03 A7 01 88 01C2 370 BISB #CLISM_QUALTRU,CLISB_QDSTAT(R7) ; MARK QUALIFIER TRUE
03EE 30 01C6 371 BSBW DCL$SETDEFVAL ; SET UP THE DEFAULT VALUE IF THERE
E1 11 01C9 372 BRB 45$ ; LOOK AT NEXT
01CB 373
01CB 374 FOR ALL QUALIFIERS NOT PRESENT, CLEAR THE ASSOCIATED BIT IN THE BIT MASK
01CB 375
01CB 376 50$: JSB @ (SP)+ ; GET NEXT DESCRIPTOR
0A 50 E9 01CD 377 BLBC R0,60$ ; BR WHEN NO MORE
F6 03 A7 00 E0 01D0 378 BBS #CLISV_QUALTRU,CLISB_QDSTAT(R7),50$ ; BR IF TRUE
02EF 30 01D5 379 BSBW DCL$CLRSETLST ; CLEAR THE BITS
F1 11 01D8 380 BRB 50$ ; LOOK FOR MORE FALSSE QUALIFIERS
01DA 381
01DA 382 FOR ALL QUALIFIERS PRESENT, TEST/SET THE ASSOCIATED BIT IN THE BIT MASK
01DA 383
01DA 384 60$: JSB @ (SP)+ ; GET NEXT QUALIFIER DESCRIPTOR
13 50 E9 01DC 385 BLBC R0,100$ ; BR WHEN NO MORE
F6 03 A7 00 E1 01DF 386 BBC #CLISV_QUALTRU,CLISB_QDSTAT(R7),60$ ; BR IF FALSE
F3 AF 9F 01E4 387 PUSHAB B^60$ ; SUBROUTINE RETURN ADDRESS
03 03 A7 01 E1 01E7 388 BBC #CLISV_QUALEXP,CLISB_QDSTAT(R7),70$ ; BR IF NOT EXPLICITLY FOUND
02B5 31 01EC 389 BRW DCL$TSTSETLST ; TEST THEN SET SET LIST, ETC.
02CC 31 01EF 390 BRW 70$: DCL$SETSETLST ; ONLY SET THE SET LIST FOR DEFAULTS
01F2 391
01F2 392 FOR ALL QUALIFIERS, CALL THE ASSOCIATED ACTION ROUTINE (IF ANY)
01F2 393
01F2 394 100$: JSB @ (SP)+ ; GET NEXT QUALIFIER DESCRIPTOR
08 50 E9 01F4 395 BLBC R0,110$ ; BR WHEN NO MORE QUALIFIERS
10 E0 01F7 396 BBS #CLISV_ALLOCCUR+<CLISB_QDFLG*8>,- ; IF ALL OCCURANCES IS SET
F7 67 01F9 397 (R7),100$ ; CALL BACK ALREADY BEEN DONE
11 10 01FB 398 BSBB QUALACT ; TAKE QUALIFIER ACTION
F3 11 01FD 399 BRB 100$ ; TRY FOR NEXT
01FF 400
01FF 401 CALL THE PARAMETER PRESENT/ABSENT ACTION ROUTINE (IF ANY)
01FF 402
01FF 403 110$: MOVL CLISA_PRSACT(R9),R1 ; PRESENT ACTION ADDRESS OFFSET
51 10 A9 D0 0203 404 120$: BEQL 130$ ; BR IF NO PARAMETER ACTION
05 13 0205 405 MOVL R9,R0 ; SET ADDRESS OF ARGUMENT TO CALL WITH
50 59 D0 0208 406 BSBB CALLBAK ; ISSUE CALL BACK
20 10 020A 407 130$: SETSTAT SUCCESS ; SET GOOD RETURN
```


RPDCL
V04-000

B 5
- RESULT PARSE MAIN ROUTINE
INPUT(N),OUTPUT(N),GETQUAL CALLBACKS

04 020D 408 140\$: RET

16-SEP-1984 00:13:01 VAX/VMS Macro V04-00
4-SEP-1984 23:42:58 [DCL.SRC]RPDCL.MAR;1

Page 10
(5)

; BACK TO DISPATCHER

```

020E 410 .SBTTL ACTION CALLBACK SUBROUTINE
020E 411 :---
020E 412 :
020E 413 FUNCTIONAL DESCRIPTION:
020E 414 :
020E 415 CALL THE USER'S ACTION ROUTINE IF SPECIFIED.
020E 416 :
020E 417 INPUTS:
020E 418 :
020E 419 R7 = ADDRESS OF QUALIFIER DESCRIPTOR BLOCK
020E 420 R10 = ADDRESS OF IMAGE LOCAL WORK AREA
020E 421 R11 = ADDRESS OF PASS 1 PARSE WORK AREA
020E 422 :
020E 423 :---
020E 424 .ENABL LSB
020E 425 :
05 02 A7 02 E1 020E 426 QUALACT:BBC #CLISV_QDEXPA,CLISB_QDFLGS(R7),5$ : BR IF ACTION ALWAYS DESIRED
2B 03 A7 01 E1 0213 427 BBC #CLISV_QUALEXP,CLISB_QDSTAT(R7),40$ : IF NOT EXPLICIT
51 10 A7 D0 0218 428 5$: MOVL CLISA_FLSACT(R7),R1 : ASSUME QUALIFIER IS FALSE
04 03 A7 00 E1 021C 429 BBC #CLISV_QUALTRU,- : BR IF THAT ASSUMPTION
51 0C A7 D0 021E 430 CLISB_QDSTAT(R7),10$ : WAS CORRECT
1C 13 0221 431 MOVL CLISA_TRUACT(R7),R1 : GET TRUE ACTION ADDRESS OFFSET
50 57 D0 0225 432 10$: BEQL 40$ : BR IF NO ACTION ROUTINE
0227 433 MOVL R7,R0 : ARGUMENT FOR CALL BACK
022A 434 :
022A 435 : ENTER HERE WITH R0 SET TO ACTION ROUTINE ADDRESS
022A 436 :
022A 437 :
022A 438 :
03 69 11 E0 022A 439 CALLBAK:BBS #CLISV_ABSADR+<CLISB_RQFLGS*8>,(R9),20$ : BR IF ADR IS ABSOLUTE
51 50 C0 022E 440 ADDL R0,R1 : RELOCATE ADDRESS
5B 6A D0 0231 441 20$: MOVL (R10),R11 : SET USER CONTEXT WORD
FDC6 CF 9F 0234 442 PUSHL R11 : PASS USER CONTEXT WORD
60 9F 0236 443 PUSHAB DCL$UTLSERV : GIVE THE ACTION ROUTINE CALL BACK ADR
61 03 FB 023A 444 PUSHAB (R0) : PASS CALLERS STRUCTURE AS ARGUMENT
5B 04 AA D0 023C 445 CALLS #3,(R1) : CALL THE ACTION ROUTINE
05 023F 446 MOVL RPW_L_DCLWRK(R10),R11 : RESET THE COMMAND WORK ADDRESS
0243 447 40$: RSB : RETURN TO MY CALLER
0244 448 :
0244 449 .DSABL LSB

```



```

0244 451 .SBTTL SCAN QUALIFIER DESCRIPTOR LIST
0244 452 :---
0244 453 :
0244 454 : FUNCTIONAL DESCRIPTION:
0244 455 :
0244 456 : THIS CO-ROUTINE IS USED TO SCAN THE UTILITY'S QUALIFIER
0244 457 : DESCRIPTOR BLOCKS LINKED TO THE CURRENT REQUEST DESCRIPTOR.
0244 458 : THE CALLER IS CALLED BACK ONCE FOR EACH QUALIFIER DESCRIPTOR
0244 459 : BLOCK UNTIL R0 IS RETURNED FALSE.
0244 460 :
0244 461 : INPUTS:
0244 462 :
0244 463 : R9 = ADDRESS OF REQUEST DESCRIPTOR BLOCK
0244 464 :
0244 465 : OUTPUTS:
0244 466 :
0244 467 : R7 = ADDRESS OF QUALIFIER DESCRIPTOR BLOCK
0244 468 : R0 = TRUE IF STILL MORE TO GO,
0244 469 : FALSE IF NO MORE LEFT
0244 470 :---
0244 471 : SCANQUAL:
0244 472 : MOVL CLISA_QUALST(R9),R7 : SCAN QUALIFIERS
0244 473 : BEQL 20$ : GET OFFSET TO QUALIFIER LIST
0244 474 : BBS #CLISV_ABSADR+<CLISB_RQFLGS*8>,(R9),10$ : BR IF NONE AT ALL
0244 475 : ADDL R9,R7 : BR IF ADR IS ABSOLUTE
0244 476 10$: SETSTAT NORMAL : ADJUST ADDRESS TO ABSOLUTE
0244 477 : TSTB (R7) : ASSUME MORE QUALIFIERS TO PROCESS
0244 478 : BEQL 20$ : END OF LIST
0244 479 : JSB @ (SP)+ : BR IF END OF LIST
0244 480 : MOVZBL CLISB_QDBLKSIZ(R7),R0 : RETURN WITH A DESCRIPTOR
0244 481 : ADDL R0,R7 : GET SIZE OF DESCRIPTOR
0244 482 : BRB 10$ : ADVANCE TO NEXT BLOCK
0244 483 20$: SETSTAT INVQUAL : CK IF MORE
0244 484 RSB0: RSB : RETURN AN ERROR
: : RETURN TO CALLER

```

```

0268 486 .SBTTL PROCESS AN INPUT/OUTPUT REQUEST
0268 487 ---
0268 488
0268 489 FUNCTIONAL DESCRIPTION:
0268 490
0268 491 THIS ROUTINE IS CALLED TO PROCESS A GIVEN INPUT OR
0268 492 OUTPUT FOR THE UTILITY. THE INPUT OR OUTPUT MAY BE
0268 493 SPECIFIED EITHER BY A PARAMETER OR QUALIFIER, DEPENDING
0268 494 ON THE COMMAND DEFINITION.
0268 495
0268 496 INPUTS:
0268 497
0268 498 R9 = ADDRESS OF REQUEST DESCRIPTOR BLOCK
0268 499 R10 = ADDRESS OF IMAGE LOCAL WORK AREA
0268 500 R11 = ADDRESS OF PASS 1 PARSE WORK AREA
0268 501
0268 502 OUTPUTS:
0268 503
0268 504 PARMPRS BIT IS SET IF INPUT/OUTPUT IS PRESENT.
0268 505 QUADWORD DESCRIPTOR DESCRIBES INPUT/OUTPUT SPECIFICATION.
0268 506 ---
0268 507 PROCIO:
04 00 EF 0268 508 EXTZV #CLISV SUBTYP,#CLISS-SUBTYP,- ; AND THE SUB TYPE VIELD
50 69 0268 509 CLISB RQTYPE(R9),R0 ; INTO R0
04 04 ED 0268 510 CMPZV #CLISV PRITYP,#CLISS PRITYP,- ; CHECK THE PRIMARY REQUEST TYPE TO
02 69 0270 511 CLISB RQTYPE(R9),#CLISK_OUTSPEC ; SEE IF REQUEST IS FOR OUTPUT
03 13 0272 512 BEQL OUTPUT ; BR IF REQUEST IS FOR OUTPUT
0121 31 0274 513 BRW INPUT ; ELSE PROCESS INPUT
0277 514
0277 515 PROCESS REQUEST FOR AN OUTPUT SPECIFICATION
0277 516
0277 517 OUTPUT:
51 D2 AB D0 0277 518 MOVL WRK_L_PAROUT(R11),R1 ; REQUEST ID FOR OUTPUT SPEC
81 50 91 0278 519 BEQL RSB0 ; SET POINTER TO OUTPUT PARSE TABLE
E5 1E 027D 520 CMPB R0,(R1)+ ; BR IF NO TABLE
0280 521 BGEQU RSB0 ; REQUEST IN RANGE?
0282 522 ; BR IF NO
0282 523
0282 524 IF THE OUTPUT PARSE INDICATOR IS NEGATIVE, THEN SIMPLY USE
0282 525 IT AS THE NEGATED PARAMETER NUMBER BY INDEXING INTO THE PARAMETER
0282 526 LIMIT TABLE.
0282 527
51 6140 98 0282 527 CVTBL (R1)[R0],R1 ; GET OUTPUT PARSE INDICATOR
F8 8F 51 91 0286 528 CMPB R1,#-CMD_K_MAX_PARMs ; PARAMETER OR QUALIFIER?
03 1B 028A 529 BLEQU 10$ ; BR IF OUTPUT IS DEFINED BY QUALIFIER
0106 31 028C 530 BRW 95$ ; ELSE IT IS A FORMAL PARAMETER
028F 531
028F 532 LOCATE THE QUALIFIER DESCRIPTOR WHICH DESCRIBES THIS OUTPUT
028F 533
FD6E' 30 028F 534 10$: BSBW DCL$GETQUALDESC ; FIND DESCRIPTOR FOR QUALIFIER #(R1)
0292 535
0292 536 IF THE QUALIFIER IS DEFAULTED TRUE, SET THE OUTPUT PRESENT AND DEFAULTED.
0292 537 NOTE THAT THE PARMPRS AND PARMDEF FLAGS HAVE ALREADY BEEN PRESET FALSE.
0292 538
18 04 A2 02 E0 0292 539 BBS #ENT_V_DEFTRUE,ENT_W_FLAGS(R2),25$ ; BR IF DEFAULTED TRUE
17 04 A2 03 E1 0297 540 BBC #ENT_V_BATDEF,ENT_Q_FLAGS(R2),30$ ; BR IF NOT BATCH DEFAULTED
05B DD 029C 541 PUSHL R11 ; SAVE WRK ADDRESS
00000000'EF 16 029E 542 JSB CLISGET_PRC ; GET ADDRESS OF PRC IN R11

```



```
50 5B D0 02A4 543      MOVL R11,R0      ; MOVE INTO R0
04 68 A0 5B 8ED0 02A7 544      POPL R11      ; RESTORE WRK ADDRESS
09 06 E1 02AA 545      BBC #PRC_V_MODE,PRC_W_FLAGS(R0),30$ ; BRANCH IF NOT BATCH JOB
03 A9 09 88 02AF 546 25$: BISB #CLISM_PARMPRS!CLISM_PARMDEF,- ; SET PARAMETER PRESENT & DEFAULT
                                CLISB_RQSTAT(R9) ; IN REQUEST STATUS BYTE
                                02B1 547
                                02B2 548
                                02B3 549 ; IF THERE IS A DEFAULT VALUE ASSOCIATED WITH THIS QUALIFIER, THEN
                                02B3 550 ; RETURN ITS DESCRIPTOR IN THE REQUEST DESCRIPTOR BLOCK. OF COURSE,
                                02B3 551 ; THIS IMPLIES THAT THE VALUE DESCRIPTOR SHOULD ONLY BE USED IF THE
                                02B3 552 ; PARMPRS BIT IS SET SINCE THE VALUE WILL ALWAYS BE THERE EVEN THOUGH
                                02B3 553 ; THE QUALIFIER IS NOT.
                                02B3 554
50 1C A2 32 02B3 555 30$: CVTWL ENT_W_DEFVAL(R2),R0 ; GET OFFSET TO DEFAULT VALUE
01 0E 13 02B7 556      BEQL 35$ ; BRANCH IF NONE
01 01 C0 02B9 557      ADDL #1,R0 ; CALCULATE ADDRESS OF COUNTED STRING
01 52 C0 02BC 558      ADDL R2,R0
08 A9 80 9A 02BF 559      MOVZBL (R0)+,CLISQ_RQDESC(R9) ; STORE LENGTH INTO VALUE DESCRIPTOR
0C A9 50 D0 02C3 560      MOVL R0,CLISQ_RQDESC+4(R9) ; AND ADDRESS
                                02C7 561
                                02C7 562 ; LOCATE THE LAST OCCURRENCE OF THE QUALIFIER ON THE COMMAND LINE
                                02C7 563
                                02C7 564 35$: CLRL -(SP) ; MAKE SPACE FOR PARAMETER LIMIT DESC
                                02C9 565      CLRL -(SP) ; SET VALUES FOR QUALIFIER TO ZERO
                                02CB 566      PUSHAB W^DCL$FNDCMDQUAL ; SET COROUTINE ADDRESS
0000'CF 9F 02CF 567 40$: JSB @ (SP)+ ; COROUTINE LINK
01 15 50 E9 02D1 568      BLBC R0,50$ ; BR IF NO MORE COMMAND QUALIFIERS
51 05 A4 91 02D4 569      CMPB PTR_B_NUMBER(R4),R1 ; IS THIS THE QUALIFIER FOR THIS OUTPUT?
04 AE 54 7D 02DA 570      BNEQ 40$ ; BR IF NO
0C AE 56 D0 02DE 571      MOVQ R4,4(SP) ; SAVE DESCRIPTOR ADDRESS AND INDEX
                                02E2 572      MOVL R6,12(SP) ; SAVE PARAMETER LIMIT DESCRIPTOR
                                02E7 573      SETBIT R5,RPW_G_BITS(R10) ; INDICATE THAT QUALIFIER WAS USED
                                02E9 574      BRB 40$ ; LOOK FOR ANOTHER OCCURANCE
                                02E9 575
                                02E9 576 ; SET THE PARMPRS AND PARMDEF FLAGS DEPENDING ON WHETHER THE
                                02E9 577 ; QUALIFIER WAS FOUND AND WHETHER IT IS NEGATED.
                                02E9 578
                                02E9 579 50$: MOVQ (SP)+,R4 ; RETREIVE PARAMETERS FOR LAST OCCURANCE
                                02EC 580      MOVL (SP)+,R6 ; RESET PARAMETER LIMIT DESCRIPTOR
                                02EF 581      BEQL 80$ ; BR IF NOT IN COMMAND EXPLICITLY
                                02F1 582      BICB #CLISM_PARMPRS!CLISM_PARMDEF,- ; CLR PARAMETER PRESENT & DEFAULT
                                02F3 583      CLISB_RQSTAT(R9) ; IN REQUEST STATUS BYTE
03 64 14 E0 02F5 584      BBS #PTR_V_NEGATE,(R4),80$ ; BR IF ASSUMED CORRECTLY
03 A9 01 88 02F9 585      BISB #CLISM_PARMPRS,CLISB_RQSTAT(R9) ; SET EXPLICITLY PRESENT
                                02FD 586
                                02FD 587 ; IF THERE IS A VALUE ON THE QUALIFIER, USE THAT VALUE
                                02FD 588
                                02FD 589
54 0C C0 02FD 589      ADDL #PTR_C_LENGTH,R4 ; ADVANCE POINTER TO NEXT DESCRIPTOR
02 FCFD' 30 0300 590      BSBW DCL$EXTRSLDESC ; TAKE DESCRIPTOR APART
01 51 91 0303 591      CMPB R1,#PTR_K_QUALVALU ; IS THIS A QUALIFIER VALUE?
01 29 13 0306 592      BEQL 70$ ; BR IF FILENAME HERE AS QUALIFIER VALUE
                                0308 593
                                0308 594 ; USE THE FILE SPECIFICATION ON THE PARAMETER FOR THIS QUALIFIER
                                0308 595 ; REMOVING THE FILE TYPE AND VERSION
                                0308 596
01 A6 55 D7 0308 597 60$: DECL R5 ; BACKUP IN RESULT PARSE DECSRIPTOR
01 29 15 030A 598      BLEQ 80$ ; BRANCH IF NO PREVIOUS PARAMETERS
01 55 91 030C 599      CMPB R5,PLM_B_FSTDESC(R6) ; IS THIS IN THE CURRENT PARAMETER
```



```

        23 19 0310 600      BLSS      80$      : BR IF NO - NO MORE TO CHECK
        03 FCEB' 30 0312 601      BSBW      DCL$GETEXTDESC : TAKE THAT DESCRIPTOR APART
        51 91 0315 602      CMPB      R1,#PTR_K_PARAMETR : WAS THIS A PARAMETER?
        EE 12 0318 603      BNEQ      60$      : BR IF NO
63 52 5D 8F 3A 031A 604      LOCC      #^A/J/,R2,(R3) : IS THERE A DIRECTORY SPEC HERE
        09 12 031F 605      BNEQ      65$      : BR IF YES
        3E 3A 0321 606      LOCC      #^A/>/,R2,(R3) : CHECK FOR ALTERNATE SYNTAX
63 52 3E 3A 0325 607      BNEQ      65$      : BR IF THAT TYPE IS HERE
        03 12 0327 608      MOVQ      R2,R0      : SET LIMITS FOR SEARCH FOR TYPE
        50 7D 032A 609 65$: LOCC      #^A/./,R0,(R1) : TRY TO FIND TYPE FIELD
61 50 2E 3A 032E 610      SUBL      R0,R2      : ADJUST LENGTH FOR FILE TYPE
        52 50 0331 611 70$: MOVQ      R2,CLISQ_RQDESC(R9) : SET RETURNED VALUE FOR NAME
        08 A9 52 7D 0335 612      :
        0335 613      : IF THE INPUT/OUTPUT WAS FOUND, THEN PROCESS ALL QUALIFIERS
        0335 614      : ASSOCIATED WITH THE PARAMETER ON WHICH IT WAS FOUND.
        0335 615      :
        5A 03 A9 00 E1 0335 616 80$: BBC      #CLISV_PARMPRS,CLISB_RQSTAT(R9),90$ : BR IF PARAMETER NOT HERE
        01CD 30 033A 617      BSBW      DCL$PROCMDQUAL : PROCESS COMMAND QUALIFIERS
        033D 618      :
        033D 619      : IF THE STRING DESCRIPTOR IS STILL NOT BEEN FILLED DESCRIBING
        033D 620      : THE OUTPUT SPECIFICATION, THEN TAKE THE PARAMETER MINUS THE
        033D 621      : FILE TYPE AND VERSION AND USE IT.
        033D 622      :
        52 02 A9 02 E0 033D 623      BBS      #CLISV_EXPNAM,CLISB_RQFLGS(R9),90$ : BR IF EXPLICIT NAMES ONLY
        08 A9 B5 0342 624      TSTW      CLISW_RQSIZE(R9) : NAME FOUND FOR THIS PARAMETER?
        4D 12 0345 625      BNEQ      90$      : BR IF YES
        56 40 AA DE 0347 626      MOVAL     RPW_G_PRMLIM(R10),R6 : POINT AT FIRST LIMIT DESCRIPTOR
        55 01 A6 9A 034B 627      MOVZBL     PLM_B_FSTDESC(R6),R5 : INDEX TO FIRST PARAMETER
        43 13 034F 628      BEQL      90$      : BRANCH IF NO PARAMETER PRESENT
        FCAC' 30 0351 629      BSBW      DCL$SETDESCADR : SET ADDRESS OF DESCRIPTOR IN R4
        FCA9' 30 0354 630      BSBW      DCL$EXTRSLDESC : TAKE THE DESCRIPTOR A PART
63 52 5D 8F 3A 0357 631      LOCC      #^A/J/,R2,(R3) : LOOK FOR A DIRECTORY SPEC
        1D 12 035C 632      BNEQ      84$      : BR IF FOUND A DIRECTORY
        3E 3A 035E 633      LOCC      #^A/>/,R2,(R3) : IF NO LOOK FOR THE OTHER DIRECTORY END
        17 12 0362 634      BNEQ      84$      : BR IF THAT DIRECTORY WAS FOUND
        3A 3A 0364 635      LOCC      #^A/./,R2,(R3) : NOW LOOK FOR DEVICE NAME
        19 13 0368 636      BEQL      86$      : BR IF NO DEVICE NAME HERE
        7E 7C 036A 637      CLRQ      -(SP) : MAKE A QUADWORD BUFFER
        6E 50 7D 036C 638 82$: MOVQ      R0,(SP) : SAVE LAST COLON WAS FOUND
        51 D6 036F 639      INCL      R1 : ADVANCE ADDRESS OVER THAT COLON
        50 D7 0371 640      DECL      R0 : SUBTRACT 1 FROM COUNT FOR THE COLON
        61 50 3A 0373 641      LOCC      #^A/./,R0,(R1) : LOOK FOR MORE COLONS
        F3 12 0377 642      BNEQ      82$      : BR IF MORE COLONS HERE
        03 BA 0379 643      POPR      #^M<R0,R1> : GET ADDRESS OF LENGTH FOR LAST COLON
        52 FF A0 9E 037B 644 84$: MOVAB     -1(R0),R2 : SET LENGTH MINUS THE TERMINATOR
        53 01 A1 9E 037F 645      MOVAB     1(R1),R3 : SET LENGTH MINUS THE TERMINATOR
        63 52 2E 3A 0383 646 86$: LOCC      #^A/./,R2,(R3) : AND ADDRESS BEYOND THE TERMINATOR
        04 12 0387 647      BNEQ      88$      : LOOK FOR A TYPE FIELD
        3B 3A 0389 648      LOCC      #^A/./,R2,(R3) : BR IF TYPE FIELD PRESENT
        52 50 C2 038D 649 88$: SUBL      R0,R2 : NOW LOOK FOR EXPLICIT VERSION
        08 A9 52 7D 0390 650 88$: MOVQ      R0,R2 : ALSO REMOVE THAT IF FOUND
        05 0394 651 90$: MOVQ      R2,CLISQ_RQDESC(R9) : SET SIZE AND ADDRESS OF DESCRIPTOR
        0395 652      : RETURN TO DISPATCHER
        0395 653      :
        0395 654      : COME HERE WHEN OUTPUT IS DEFINED BY A NEGATED PARAMETER NUMBER
        0395 655      :
        0395 656      :
```



```
50 51 D2 0395 657 95$: MCOML R1,R0 ; GET POSITIVE OUTPUT NUMBER - 1
      0398 658 ; BASED AT ZERO (P1=0)
      0398 659
      0398 660
      0398 661 : COME HERE WHEN INPUT IS REQUESTED (MUST BE A PARAMETER)
      0398 662 :
      0398 663
56 40 AA40 DE 0398 664 INPUT: MOVAL RPW_G_PRMLIM(R10)[R0],R6; GET ADDRESS OF PARAMETER LIMIT ENTRY
      039D 665
      039D 666
      039D 667 : RETURN THE VALUE OF THE PARAMETER DESCRIBED BY THE PARAMETER
      039D 668 : LIMIT MARKER POINTED TO BY R6. ALSO, PROCESS ALL QUALIFIERS
      039D 669 : ASSOCIATED WITH THE PARAMETER.
      039D 670 :
      039D 671
      039D 672
      039D 673
      03A0 674
      03A3 675
      03A7 676
      03A9 677
      03AB 678
      03AD 679
      03B0 680 10$:
      03B3 681
      03B6 682
      03B9 683
      03BC 684
      03BE 685 20$:
      03C2 686
      03C4 687
      03C7 688
      03CA 689
      03CC 690
      03CE 691
      03D0 692
      03D3 693 30$:
      03D5 694
      03D8 695
      03DA 696
      03DC 697
      03DE 698
      03E0 699
      03E2 700
      03E4 701 90$:
      03E6 702 RET1:
      03E7 703

FC60' 30 BSBW DCL$EXTNXTDESC ; TAKE NEXT DESCRIPTOR APART
43 50 E9 03A0 673 BLBC R0,90$ ; ALL DONE
08 A9 52 7D 03A3 674 MOVQ R2,CLISQ_RQDESC(R9) ; SAVE ADDRESS OF PARAMETER
      01 88 03A7 675 BISB #CLISM_PARMPRS - ; SET FLAG THAT PARAMETER IS PRESENT
      03 A9 03A9 676 CLISB_RQSTAT(R9) ; IN USERS REQUEST STATUS BYTE
      56 DD 03AB 677 PUSHL R6 ; SAVE PARAMETER DESCRIPTOR POINTER
      015A 30 03AD 678 BSBW DCL$PROCMDQUAL ; TAKE CARE OF COMMAND QUALIFIERS
      56 8ED0 03B0 679 POPL R6 ; RESTORE PARM LIMIT DESCRIPTOR POINTER
      FC4A' 30 03B3 680 10$: BSBW DCL$EXTNXTDESC ; TAKE THE NEXT DESCRIPTOR APART
      2D 50 E9 03B6 681 BLBC R0,90$ ; BR IF NO MORE
      01 51 91 03B9 682 CMPB R1,#PTR_K_PARMQUAL ; IS THIS A PARAMETER QUALIFIER
      17 12 03BC 683 BNEQ 30$ ; BR IF NO
      FE82 CF 9F 03BE 684 PUSHAB SCANQUAL ; SET INITIAL COROUTINE ADDRESS
      9E 16 03C2 685 20$: JSB @ (SP)+ ; GET NEXT DESCRIPTOR
      20 50 E9 03C4 686 BLBC R0,RET1 ; NO FIND IS AN ERROR
      05 A4 91 03C7 687 CMPB PTR_B_NUMBER(R4),- ; IS THIS THE QUALIFIER DESCRIPTOR?
      01 A7 03CA 688 CLISB_QDCODE(R7)
      F4 12 03CC 689 BNEQ 20$ ; IF NO LOOK AT NEXT
      8E D5 03CE 690 TSTL (SP)+ ; CLEAR COROUTINE ADDRESS
      0187 30 03D0 691 BSBW DCL$HANDLQUAL ; SET UP QUALIFER RESULT PARSE DATA
      DE 11 03D3 692 BRB 10$ ; CHECK FOR MORE
      03 51 91 03D5 693 30$: CMPB R1,#PTR_K_PARAMETR ; THE NEXT PARAMETER
      D9 12 03D8 694 BNEQ 10$ ; BR IF NO
      66 97 03DA 695 DECB PLM_B_NXTDESC(R6) ; BACK UP INDEX FOR NEXT RESULT PARSE
      66 91 03DC 696 CMPB PLM_B_NXTDESC(R6),- ; CHECK IF NEXT IS LEQ LAST,
      02 A6 03DE 697 PLM_B_LSTDESC(R6) ; IN THE CURRENT PARAMETER
      04 1A 03E0 698 BGTRU 90$ ; IF GTRU, NO MORE ELEMENTS IN THIS SET
      02 88 03E2 699 BISB #CLISM_CONCATINP,- ; SET FLAG TO SAY CONCATONATED INPUT
      03 A9 03E4 700 CLISB_RQSTAT(R9) ; LIST IS NO EXHAUSTED.
      05 03E6 701 90$: RSB ; BACK TO I/O PROCESSOR
      04 03E7 702 RET1: RET
```

```
03E8 704 .SBTTL VALUE CONVERSION ROUTINES
03E8 705 :++
03E8 706 : FUNCTIONAL DESCRIPTION:
03E8 707 :
03E8 708 : THIS ROUTINE IS CALLED WHEN THE UTILITY HAS REQUESTED
03E8 709 : A QUALIFIER VALUE CONVERSION.
03E8 710 :
03E8 711 : CALLING SEQUENCE:
03E8 712 :
03E8 713 : ENTERED VIA A CASE FOLLOWING A CALL
03E8 714 :
03E8 715 : INPUT PARAMETERS:
03E8 716 :
03E8 717 : R9 = ADDRESS OF REQUEST DESCRIPTOR FOR VALUE CONVERSION
03E8 718 : R10 = ADDRESS OF IMAGE LOCAL WORK AREA
03E8 719 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
03E8 720 :
03E8 721 : OUTPUT PARAMETERS:
03E8 722 :
03E8 723 : VALUE IS CONVERTED AND STRING DESCRIPTOR IN QUALFIER DESCRIPTOR
03E8 724 : IS UPDATED TO DESCRIBE THE REMAINING VALUE-IF ANY.
03E8 725 :
03E8 726 : COMPLETION CODES:
03E8 727 :
03E8 728 : DCL$NORMAL FOR SUCCESSFUL CONVERSION
03E8 729 : DCL$VALCNVERR FOR CONVERSION ERROR
03E8 730 : DCL$NOVALUE IF VALUE NOT PRESENT
03E8 731 :
03E8 732 :--
03E8 733 :
03E8 734 DCL$VALCNV:
57 0C AC D0 03E8 735 MOVL 12(AP),R7 : REQUEST FOR VALUE CONVERSION
52 04 A7 7D 03EC 736 SETINTR NOVALUE : GET QUALIFIER DESCRIPTOR
59 13 03F3 737 MOVQ CLISQ_QDVALDESC(R7),R2 : ASSUME NO VALUE PRESENT
7E 7C 03F7 738 BEQL 40$ : COPY QUALIFIER VALUE STRING DESCRIPTOR
55 53 D0 03F9 739 CLRQ -(SP) : BR IF NO VALUE
54 F492 CB DE 03FB 740 MOVL R3,R5 : ASSUME NOT CONVERTING DEFAULT VALUE
55 54 C2 03FE 741 MOVAL WRK_G_BUFFER(R11),R4 : COPY ADDRESS OF STRING
54 F9B6 CB DE 0403 742 SUBL R4,R5 : BASE ADDRESS OF BUFFER
51 F4 A4 DE 0406 743 MOVAL WRK_G_RESULT(R11),R4 : FIND BYTE OFFSET INTO BUFFER
OC 08 ED 040B 744 MOVAL -PTR_C_LENGTH(R4),R1 : RESULT PARSE BUFFER
55 64 040F 745 10$: CMPZV #PTR_V_OFFSET,#PTR_S_OFFSET : SET INDEX BASE INTO RESULT BUFFER
55 64 0412 746 (R4),R5 :
55 54 OC 12 0414 747 BNEQ 20$ : IS THIS THE DESCRIPTOR?
55 54 51 C3 0416 748 SUBL3 R1,R4,R5 : BR IF FOUND THE DESCRIPTOR
55 54 OC C6 041A 749 DIVL #PTR_C_LENGTH,R5 : FIND BYTE OFFSET TO DESCRIPTOR
FBE0 30 041D 750 BSBW DCL$EXTRSLDESC : NOW PTR INDEX INTO RESULT BUFFER
22 11 0420 751 BRB 30$ : TAKE RESULT DESCRIPTOR APART
54 OC C0 0422 752 20$: ADDL #PTR_C_LENGTH,R4 : PROCESS THE REQUEST WITH USER VALUE
B6 AB 54 D1 0425 753 CMPL R4,WRK_L_RSLEND(R11) : ADVANCE TO NEXT DESCRIPTOR
E4 1F 0429 754 BLSSU 10$ : IS THIS THE LAST DESCRIPTOR?
63 52 2C 3A 042B 755 SETBIT #31,(SP) : BR IF NO
OF 13 0433 756 LOCC #^A/,/,R2,(R3) : SET FLAG FOR INTERNAL VALUE
52 50 C2 0435 757 BEQL 30$ : CHECK FOR MULTIPLE VALUES
6E 50 01 A3 0438 758 SUBL R0,R2 : BR IF LAST VALUE VALUES
04 AE 53 52 C1 043C 759 SUBW3 #1,R0,(SP) : FIND LENGTH OF CURRENT VALUE
760 ADDL3 R2,R3,4(SP) : SET REMAINING LENTH
: FIND ADDRESS OF COMMA
```



```
04 AE D6 0441 761 INCL 4(SP) ; PLUS 1 TO START OF REAL VALUE
0444 762 30$: CASE CLISB_RQTYPE(R9),- ; DECODE REQUEST TYPE
0444 763 ; TYPE=B,- ; CASE ON A BYTE
0444 764 LIMIT=#CLISK_NUMERVAL,<- ; LOWEST REQUEST FOR VALUE LEGAL
0444 765 50$,- ; NUMERIC CONVERSION
0444 766 100$,- ; ASCII VALUE
0444 767 >
044D 768 SETSTAT INVREQTYP ; INCORRECT VALUE
51 01 04 0452 769 40$: RET ; EXIT CONVERSION
FBA7 01 D0 0453 770 50$: MOVL #PRC_K_DEC,R1 ; SET RADIX=DECIMAL
30 0456 771 BSBW DCL$CNVNOEDIT ; CONVERT NUMERIC
06 12 0459 772 BNEQ 70$ ; IF NOT EQUAL - CONVERSION ERROR
OC A9 51 D0 045B 773 MOVL R1,CLISL_RQVALU(R9) ; SET RESULTANT VALUE
1D 11 045F 774 BRB 120$ ; EXIT CONVERSION
0461 775 70$: SETSTAT VALCNVERR ; SET ERROR
6E B4 0466 776 CLRW (SP) ; ZERO ANY BYTE COUNT HERE IF ANY
50 6E C8 0468 777 BISL (SP),R0 ; INCLUDE INTERNAL BIT IF THERE
04 046B 778 RET ; RETURN TO DISPATCHER
046C 779
046C 780 ;
046C 781 ; REQUEST ASCII STRING VALUE
046C 782 ;
046C 783
F4 AF 08 A9 52 3D 3A 046C 784 90$: .ASCII \:=\ ; TERMINATORS FOR KEYVALUES
02 6243 7D 046E 785 100$: MOVQ R2,CLISQ_RQDESC(R9) ; SET ADDRESS AND SIZE OUTPUT VALUE
04 13 0472 786 LOCC (R2)[R3],#2,90$ ; CHECK FOR KEY VALUE
03 A9 02 88 0478 787 BEQL 120$ ; BR IF NONE LEFT IN MATCH
04 A7 8E 7D 047A 788 BISB #CLISM_KEYVALU,CLISB_RQSTAT(R9) ; INDICATE SUBVALUE FOLLOWING
03 04 A7 1F E4 047E 789 120$: MOVQ (SP)+,CLISQ_QDVALDESC(R7) ; GET DEFAULT VALUE INFORMATION BACK
00F6 30 0482 790 BBSC #31,CLISQ_QDVALDESC(R7),140$ ; BR IF DOING DEFAULT VALUE
52 04 A7 7D 048A 791 BSBW DCL$SETQUAVAL ; SET UP DESCRIPTOR FOR REMAINING VALUE
10 13 0487 792 140$: MOVQ CLISQ_QDVALDESC(R7),R2 ; GET REMAINING VALUE
03 A9 01 88 048E 793 BEQL 150$ ; BR IF THERE IS NONE
0494 794 BISB #CLISM_MOREVALS,CLISB_RQSTAT(R9) ; SET FLAG TO INDICATE MORE
03 02 A9 00 E0 049A 795 SETINTR ILLVAL ; ASSUME THAT NO MORE ALLOWED
04A0 796 BBS #CLISV_LASTVAL,CLISB_RQFLGS(R9),RET2 ; BR IF ERROR
04A3 797 150$: SETSTAT SUCCESS ; INDICATE GOOD STATUS
798 RET2: RET ; ALL DONE
```

```

04A4 800 .SBTTL PROCESS BIT LISTS
04A4 801 :++
04A4 802 : FUNCTIONAL DESCRIPTION:
04A4 803 :
04A4 804 : THESE ROUTINES ARE CALLED TO PROCESS THE BIT LISTS SUPPLIED
04A4 805 : WITH A PARAMETER QUALIFIER. THERE ARE 3 LISTS, THE TEST, SET
04A4 806 : AND CLEAR LISTS. THE TEST LIST IS INTENDED TO DETECT CONFLICTING
04A4 807 : QUALIFIERS AND IS TESTED ONLY WHEN THE QUALIFIER IS FOUND
04A4 808 : EXPLICITLY TRUE IN THE COMMAND. THE SET LIST IS SET WHEN THE
04A4 809 : QUALIFIER IS FOUND TO BE TRUE, CLEARED WHEN THE QUALIFIER IS
04A4 810 : FOUND TO BE FALSE. THE CLEAR LIST INDICATES A SET OF BITS THAT
04A4 811 : SHOULD BE CLEARED IF THE QUALIFIER IS TRUE. THIS PERMITS
04A4 812 : THE PRESENTS OF A QUALIFIER TO OVERRIDE THE PRESENTS OF
04A4 813 : ANOTHER.
04A4 814 :
04A4 815 : CALLING SEQUENCE:
04A4 816 :
04A4 817 : BSB/JSB DCL$SETSETLST ; SET THE SET LIST, CLEAR THE CLEAR LIST
04A4 818 : BSB/JSB DCL$CLRSETLST ; CLEAR THE SET LIST, SET THE CLEAR LIST
04A4 819 : BSB/JSB DCL$TSTSETLST ; TEST THE TEST LIST, THEN DO SETSETLST
04A4 820 :
04A4 821 : INPUT PARAMETERS:
04A4 822 :
04A4 823 : R7 CONTAINS THE ADDRESS OF THE PROPER QUALIFIER DESCRIPTOR
04A4 824 : R8 = ADDRESS OF UTILITY BIT ARRAY
04A4 825 : R9 = ADDRESS OF REQUEST DESCRIPTOR
04A4 826 : R10 = ADDRESS OF WORK BLOCK
04A4 827 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
04A4 828 :
04A4 829 : OUTPUT PARAMETERS:
04A4 830 :
04A4 831 : THE BITS ARE SET/CLEARED
04A4 832 :
04A4 833 : SIDE EFFECTS:
04A4 834 :
04A4 835 : TOP LEVEL ERROR IS ISSUED IF BIT TEST FAILURE
04A4 836 :--
04A4 837 : .ENABL LSB
04A4 838 :
04A4 839 DCL$TSTSETLST::
04A4 840 MOVAB CLISC QDBITS(R7),R2 ; TEST THE TEST LIST, THEN DO SET LIST
04A4 841 BBC #CLISQ_QDUSRV,CLISB_QDFLGS(R7),5$ ; GET ADDRESS OF BIT TEST LIST
04A4 842 TSTL (R2)+ ; BR IF NO USER CONTEX VALUE
04A4 843 5$: MOVZBL (R2)+,R1 ; SKIP OVER THE USERS VALUE
04A4 844 BEQL DCL$SETSETLST ; GET COUNT OF BITS TO TEST
04A4 845 10$: MOVZBL (R2)+,R3 ; GO SET THE BITS
04A4 846 BBS R3,(R8),100$ ; GET BIT NUMBER
04A4 847 SOBGTR R1,10$ ; TAKE ERROR EXIT
04A4 848 ; BR IF MORE TO DO
04A4 849 DCL$SETSETLST::
04A4 850 MOVL #1,R0 ; SET THE SET LIST
04A4 851 BSBB 50$ ; SET A TRUE INDICATOR
04A4 852 CLRL R0 ; PROCESS SET LIST
04A4 853 BRB 60$ ; NOW A FALSE
04A4 854 ; AND DO CLEAR LIST
04A4 855 DCL$CLRSETLST::
04A4 856 CLRL R0 ; CLEAR THE SET LIST
04A4 857 ; GET A FALSE

```



```

02 52 14 A7 9E 04C9 857 : BSBB 50$ : CLEAR THE SET LIST
02 02 A7 01 E1 04C9 858 : INCL R0 : NOW TRUE
      82 D5 04C9 859 : BRB 60$ : SET THE CLEAR LIST
      51 82 9A 04C9 860 :
      52 51 9A 04C9 861 50$: MOVAB CLISC_QDBITS(R7),R2 : GET ADDRESS OF TEST LIST
      51 82 9A 04CD 862 : BBC #CLISV_QDUSRV,CLISB_QDFLG(R7),55$ : BR IF NO USER VALUE PRESENT
      11 13 9A 04D2 863 : TSTL (R2)+ : SKIP USER CONTEX LONGWORD
      82 9A 04D4 864 55$: MOVZBL (R2)+,R1 : GET COUNT OF TEST LIST
      53 82 9A 04D7 865 : ADDL R1,R2 : AND SKIP OVER THE LIST
      04 50 E8 04DA 866 60$: MOVZBL (R2)+,R1 : GET COUNT OF SET LIST
      EF 51 F5 04DD 867 : BEQL 90$ : BR IF NONE
      05 04DF 868 70$: MOVZBL (R2)+,R3 : GET A BIT
      04E2 869 : SETBIT R3,(R8) : SET THE BIT
      04E6 870 : BLBS R0,80$ : BR IF THAT WAS THE CORRECT ACTION
      04E9 871 : CLRBIT R3,(R8) : ELSE CLEAR IT
      04ED 872 80$: SOGTR R1,70$ : DO ALL BITS
      04F0 873 90$: RSB : RETURN
      04F1 874 :
      04F1 875 : COME HERE WHEN A CONFLICTING QUALIFIER IS FOUND.
      04F1 876 : SET ERROR RETURN STRING INFO TO POINT AT THE QUALIFIER
      04F1 877 :
      04F1 878 :
      55 D4 04F1 879 100$: CLRL R5 : INIT FOR SEARCH
      55 D6 04F3 880 110$: INCL R5 : INCREASE INDEX BY 1
      FB08' 30 04F5 881 : BSBW DCL$GETEXTDESC : THAT THE DESCRIPTOR APART
      04F8 882 : ASSUME PTR_K_CMDQUAL EQ 0
      04F8 883 : ASSUME PTR_K_PARMQUAL EQ 1
      01 51 D1 04F8 884 : CMPL R1,PTR_K_PARMQUAL : IS THIS A QUALIFIER
      01 F6 1A 04FB 885 : BGTRU 110$ : BR IF NO
      05 A7 91 04FD 886 : CMPB CLISB_QDCODE(R7),- : IS IT THE ONE THAT CONFLICTED?
      05 A4 EF 12 0500 887 : PTR_B_NUMBER(R4)
      0502 888 : BNEQ 110$ : BR IF NO
      0504 889 : SETSTAT CONQUAL : SET ERROR TO CONFLICTING QUALIFERS
      0509 890 : RET : REPORT THE ERROR
      050A 891 :
      050A 892 : .DSABL LSB

```

```

050A 894 .SBTTL PROCESS ALL QUALIFIERS IN QUALIFIER LIST
050A 895 :++
050A 896 : FUNCTIONAL DESCRIPTION:
050A 897 :
050A 898 : THIS ROUTINE IS CALLED WHEN A PARAMETER HAS BEEN FOUND PRESENT
050A 899 : IN THE COMMAND. THIS ROUTINE SEARCHED FOR ANY COMMAND QUALIFIERS
050A 900 : PRESENT ITN THE RANGE OF THE COMMAND, WHERE THE RANGE OF THE
050A 901 : COMMAND IS DEFINED AS ON THE VERB, OR WITHIN THE CURRENT LIMITS
050A 902 : OF ANY COMMAND PARAMETERS. ONLY QUALIFIERS EXPLICITLY REQUESTED
050A 903 : ARE PROCESSED.
050A 904 :
050A 905 : CALLING SEQUENCE:
050A 906 :
050A 907 : BSB/JSB DCL$PROCMDQUAL
050A 908 :
050A 909 : INPUT PARAMETERS:
050A 910 :
050A 911 : R8 = ADDRESS OF UTILITY BIT ARRAY
050A 912 : R9 = ADDRESS OF REQUEST DESCRIPTOR
050A 913 : R10 = ADDRESS OF WORK BLOCK
050A 914 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
050A 915 :
050A 916 : OUTPUT PARAMETERS:
050A 917 :
050A 918 : ALL QUALIFIERS SPECIFIED BY THE UTILITY, AND PRESENT ARE PROCESSED.
050A 919 :
050A 920 :--
050A 921 :
050A 922 DCL$PROCMDQUAL::
050A 923 : PROCESS COMMAND QUALIFIERS
050A 924 : INIT COROUTINE
050A 925 : FIND NEXT QUALIFIER IN COMMAND
050A 926 : BR IF NO MORE
050A 927 : SCAN THE UTILITIES QUALIFIERS
050A 928 : FIND NEXT QUALIFIER DESCRIPTOR BLOCK
050A 929 : BR IF NO MORE UTILITY DESCRIPTORS
050A 930 : MATCH UTILITY CODE?
050A 931 :
050A 932 : BR IF NO-CHECK UTILITIES NEXT DESCPTR
050A 933 : CLR QUAL DESC SCAN COROUTINE
050A 934 : SAVE INFO USED BY COROUTINE
050A 935 : #CLISV_ALLOCCUR+<CLISB_QDF LGS*8>,- : BR IF UTILITY WANTS TO SEE
050A 936 : (R7),60$ : ALL OCCURANCES OF THIS QUALIFIER
050A 937 : SETBIT R5,RPW_G_BITS(R10) : INDICATE QUALIFIER PROCESSED
050A 938 : PUSHL 12(SP) : COPY COROUTINE ADDRESS
050A 939 : JSB @ (SP)+ : CONTINUE SCAN FOR THIS QUALIFIER
050A 940 : BLBC R0,40$ : BR IF NO MORE OCCURANCES
050A 941 : CMPB CLISB_QDCODE(R7),- : IS THIS THE SAME QUALIFIER?
050A 942 : PTR_B_NUMBER(R4) :
050A 943 : BNEQ 30$ : IF NO LOOK SOME MORE
050A 944 : POPR #^M<R0,R4,R5,R6> : POP RETURN ADDRESS PLUS PARAMETERS
050A 945 : BRB 10$ : PROCESS THIS WHEN WE FIND IT AGAIN
050A 946 : MOVQ (SP),R4 : SET THE VALUE OF QUALIFIER DESCRIPTOR
050A 947 : DCL$HANDLQUAL : HANDLE THE QUALIFIER
050A 948 : POPR #^M<R4,R5,R6> : RESTORE INFO USED BY COROUTINE
050A 949 : BBC #CLISV_ALLOCCUR+<CLISB_QDF LGS*8>,(R7),10$ : DOING ALL OCCURANCES
050A 950 : BSBW QUALACT : IF YES TAKE ACTION AT THIS TIME
050A 951 : BRB 10$ : LOOK FOR MORE

```


RPDCL
V04-000

N 5
- RESULT PARSE MAIN ROUTINE
PROCESS ALL QUALIFIERS IN QUALIFIER LIST
05 0559 951 80\$: RSB
16-SEP-1984 00:13:01 VAX/VMS Macro V04-00
4-SEP-1984 23:42:58 [DCL.SRC]RPDCL.MAR;1

Page 22
(11)

```

055A 953      .SBTTL PROCESS QUALIFIER
055A 954      :++
055A 955      : FUNCTIONAL DESCRIPTION:
055A 956      :
055A 957      :     THIS ROUTINE IS CALLED TO PROCESS A QUALIFIER FOUND IN THE
055A 958      :     COMMAND LINE, AND SET ALL UTILITY STRUCTURES CORRECTLY.
055A 959      :
055A 960      : CALLING SEQUENCE:
055A 961      :
055A 962      :     BSB/JSB DCL$HANDLQUAL
055A 963      :
055A 964      : INPUT PARAMETERS:
055A 965      :
055A 966      :     R4 CONTAINS THE ADDRESS OF THE RESULT PARSE DESCRIPTOR FOR THE QUALIFIER
055A 967      :     R5 IS INDEX TO THE RESULT DESCRIPTOR FOR THE QUALIFIER
055A 968      :     R7 CONTAINS THE ADDRESS OF THE UTILITY QUALIFIER DESCRIPTOR
055A 969      :
055A 970      : IMPLICIT INPUTS:
055A 971      :
055A 972      :     R8 = ADDRESS OF UTILITY BIT ARRAY
055A 973      :     R9 = ADDRESS OF REQUEST DESCRIPTOR
055A 974      :     R10 = ADDRESS OF WORK BLOCK
055A 975      :     R11 = ADDRESS OF PASS 1 PARSE WORK AREA
055A 976      :
055A 977      : OUTPUT PARAMETERS:
055A 978      :
055A 979      :     UTILITY QUALIFIER DATA STRUCTURE IS SET PROPERLY
055A 980      :
055A 981      :--
055A 982      : .ENABL LSB
055A 983
055A 984 DCL$HANDLQUAL::
055A 985      CLRQ      CLISQ QDVALDESC(R7)      : PROCESS A QUALIFIER
055A 986      SETBIT    R5,RPO_G BITS(R10)      : SET VALUE TO NONE
055A 987      BISB      #CLISM_QDALEXP,-        : COUNT THIS QUALIFIER AS PROCESSED
055A 988      CLISB QDSTAT(R7)      : SET FLAG TO INDICATE QUALIFIER WAS
055A 989      BICB      #CLISM_QUALTRU,CLISB_QDSTAT(R7) : AND SET STATE TO FALSE
055A 990      BBS       #PTR_V_NEGATE,-        : BR IF THE ASSUMED STATE,FALSE,
055A 991      PTR C_DESCR(R4),40$      : BR IF ASSUMED CORRECTLY
055A 992      BISB      #CLISM_QUALTRU,-        : ASSUMED INCORRECTLY, SET STATE OF
055A 993      CLISB QDSTAT(R7)      : QUALIFIER TO TRUE
055A 994      CMPZV     #PTR_V_TERM,#PTR_S_TERM,- : TERMINATOR YIELD LIMITS
055A 995      PTR C_DESCR(R4),#PTR_K_COLON : EXPLICIT VALUE GIVEN?
055A 996      BEQL      DCL$SETQUALVAL      : BR IF YES, SET USER SPECIFIED VALUE
055A 997      CMPZV     #PTR_V_TERM,#PTR_S_TERM,- : TERMINATOR YIELD LIMITS
055A 998      PTR C_DESCR(R4),#PTR_K_LPAREN : EXPLICIT VALUE GIVEN?
055A 999      BNEQ      70$      : BR IF NO, SET DEFAULT IF THERE IS ONE
0580 1000 : DROP THRU TO RETURN EXPLICIT OR DEFAULT VALUE (IF ANY)

```



```
0580 1002 .SBTTL RETURN EXPLICIT QUALIFIER VALUE
0580 1003 :++
0580 1004 : FUNCTIONAL DESCRIPTION:
0580 1005 :
0580 1006 : THIS ROUTINE IS CALLED TO SET THE STRING LIMITS OF
0580 1007 : A EXPLICIT VALUE ENTERED VIA THE COMMAND STREAM.
0580 1008 :
0580 1009 : CALLING SEQUENCE:
0580 1010 :
0580 1011 : BSB/JSB DCL$SETQUALVAL
0580 1012 :
0580 1013 : INPUT PARAMETERS:
0580 1014 :
0580 1015 : R5 IS INDEX TO THE RESULT DESCRIPTOR FOR THE QUALIFIER OR LAST VALUE
0580 1016 : R7 CONTAINS THE ADDRESS OF THE UTILITY QUALIFIER DESCRIPTOR
0580 1017 :
0580 1018 : IMPLICIT INPUTS:
0580 1019 :
0580 1020 : R8 = ADDRESS OF UTILITY BIT ARRAY
0580 1021 : R9 = ADDRESS OF REQUEST DESCRIPTOR
0580 1022 : R10 = ADDRESS OF WORK BLOCK
0580 1023 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
0580 1024 :
0580 1025 : OUTPUT PARAMETERS:
0580 1026 :
0580 1027 : UTILITY QUALIFIER DATA STRUTURE IS SET PROPERLY
0580 1028 :
0580 1029 : ---
0580 1030 DCL$SETQUALVAL:
0580 1031 CLRQ CLISQ_QDVALDESC(R7) : SET QUALIFIER VALUE ONLY
0580 1032 INCL R5 : ASSUME NO VALUE PRESENT
0580 1033 BSBW DCL$GETTEXTDESC : ADV INDEX TO NEXT RESULT DESCRIPTOR
0580 1034 CMPB R1,#PTR_K_QUALVALU : TAKE THAT 1 APART
0580 1035 BNEQ 40$ : WAS THIS A VALUE?
0580 1036 PUSHF #M<R2,R3> : BR IF NO
0580 1037 BRB 20$ : SET CURRENT LIMIT VALUES
0580 1038 10$: INCL R5 : JOIN COMMON LOOP
0580 1039 BSBW DCL$GETTEXTDESC : ADD 1 TO INDEX INTO RESULT BUFFER
0580 1040 CMPB R1,#PTR_K_QUALVALU : TAKE THE DESCRIPTOR APART
0580 1041 BNEQ 30$ : LAST VALUE IN LIST?
0580 1042 ADDL3 R2,R3,(SP) : BR IF YES-EXIT THE LOOP
0580 1043 BRB 10$ : FIND END OF LAST VALUE
0580 1044 30$: POPR #M<R2,R3> : LOOK FOR MORE
0580 1045 SUBL R3,R2 : GET VALUE LIMITS BACK
0580 1046 MOVQ R2,CLISQ_QDVALDESC(R7) : CHANGE TO LENGTH
0580 1047 40$: RSB : SET VALUE
0580 1048 05AB 1048 : PROCESS BIT LISTS-RETURN FROM THERE
0580 1049 70$: CMPB (R9),#CLISK_GETOPT : IS THIS AN OPTIONS PARSE
0580 1050 BEQL 80$ : BR IF SO - NO DEFAULT VALUES THEN
0580 1051 MOVZBL PTR B NUMBER(R4),R1 : GET QUALIFIER NUMBER
0580 1052 BSBW DCL$GETPARMQUAL : LOCATE ASSOCIATED QUALIFIER BLOCK
0580 1053 : DROP THRU TO RETURN THE QUALIFIER DEFAULT VALUE (IF ANY)
```

04 A7 7C 0580 1031 CLRQ CLISQ_QDVALDESC(R7) : SET QUALIFIER VALUE ONLY
55 D6 0583 1032 INCL R5 : ASSUME NO VALUE PRESENT
FA78' 30 0585 1033 BSBW DCL\$GETTEXTDESC : ADV INDEX TO NEXT RESULT DESCRIPTOR
02 51 91 0588 1034 CMPB R1,#PTR_K_QUALVALU : TAKE THAT 1 APART
1D 12 058B 1035 BNEQ 40\$: WAS THIS A VALUE?
OC BB 058D 1036 PUSHF #M<R2,R3> : BR IF NO
OA 11 058F 1037 BRB 20\$: SET CURRENT LIMIT VALUES
55 D6 0591 1038 10\$: INCL R5 : JOIN COMMON LOOP
FA6A' 30 0593 1039 BSBW DCL\$GETTEXTDESC : ADD 1 TO INDEX INTO RESULT BUFFER
02 51 91 0596 1040 CMPB R1,#PTR_K_QUALVALU : TAKE THE DESCRIPTOR APART
06 12 0599 1041 BNEQ 30\$: LAST VALUE IN LIST?
6E 53 52 C1 059B 1042 20\$: ADDL3 R2,R3,(SP) : BR IF YES-EXIT THE LOOP
F0 11 059F 1043 BRB 10\$: FIND END OF LAST VALUE
OC BA 05A1 1044 30\$: POPR #M<R2,R3> : LOOK FOR MORE
52 53 C2 05A3 1045 SUBL R3,R2 : GET VALUE LIMITS BACK
04 A7 52 7D 05A6 1046 MOVQ R2,CLISQ_QDVALDESC(R7) : CHANGE TO LENGTH
05 05AA 1047 40\$: RSB : SET VALUE
05AB 1048 : PROCESS BIT LISTS-RETURN FROM THERE
03 69 91 05AB 1049 70\$: CMPB (R9),#CLISK_GETOPT : IS THIS AN OPTIONS PARSE
1B 13 05AE 1050 BEQL 80\$: BR IF SO - NO DEFAULT VALUES THEN
51 05 A4 9A 05B0 1051 MOVZBL PTR B NUMBER(R4),R1 : GET QUALIFIER NUMBER
FA49' 30 05B4 1052 BSBW DCL\$GETPARMQUAL : LOCATE ASSOCIATED QUALIFIER BLOCK
05B7 1053 : DROP THRU TO RETURN THE QUALIFIER DEFAULT VALUE (IF ANY)


```
05B7 1055 .SBTTL RETURN QUALIFIER DEFAULT VALUE
05B7 1056 :++
05B7 1057 : FUNCTIONAL DESCRIPTION:
05B7 1058 :
05B7 1059 : THIS ROUTINE IS CALLED TO SET THE STRING LIMITS FOR
05B7 1060 : A DEFAULT VALUE ASSOCIATED WITH A QUALIFIER THAT IS TRUE.
05B7 1061 :
05B7 1062 : CALLING SEQUENCE:
05B7 1063 :
05B7 1064 : BSB/JSB DCL$SETDEFVAL
05B7 1065 :
05B7 1066 : INPUT PARAMETERS:
05B7 1067 :
05B7 1068 : R2 CONTAINS THE ADDRESS OF DCL INTERNAL QUALIFIER DESCRIPTOR
05B7 1069 : R7 CONTAINS THE ADDRESS OF THE UTILITY QUALIFIER DESCRIPTOR
05B7 1070 :
05B7 1071 : IMPLICIT INPUTS:
05B7 1072 :
05B7 1073 : R8 = ADDRESS OF UTILITY BIT ARRAY
05B7 1074 : R9 = ADDRESS OF REQUEST DESCRIPTOR
05B7 1075 : R10 = ADDRESS OF WORK BLOCK
05B7 1076 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
05B7 1077 :
05B7 1078 : OUTPUT PARAMETERS:
05B7 1079 :
05B7 1080 : UTILITY QUALIFIER DATA STRUTURE IS SET PROPERLY
05B7 1081 :
05B7 1082 : ---
05B7 1083 DCL$SETDEFVAL:
50 1C A2 32 05B7 1084 CVTWL ENT_W_DEFVAL(R2),R0 ; RETURN QUALIFER DEFAULT VALUE
50 0E 13 05BB 1085 BEQL 80$ ; GET OFFSET TO DEFAULT VALUE STRING
50 01 C0 05BD 1086 ADDL #1,R0 ; BR IF NO DEFAULT VALUE
50 52 C0 05C0 1087 ADDL R2,R0 ; FIND REAL ADDRESS OF DEFAULT VALUE
04 A7 80 9B 05C3 1088 MOVZBW (R0)+,CLISW_QDVALSIZ(R7) ; SET SIZE OF VALUE STRING
08 A7 50 D0 05C7 1089 MOVL R0,CLISA_QDVALADR(R7) ; AND THE ADDRESS OF THE STRING
05 05CB 1090 RSB 80$ ; RETURN FROM DEFAULT VALUE PROCESSING
05CC 1091
05CC 1092 .DSABL LSB
```


	C3	AB	95
		32	13
54	F9B6	CB	9E
		1C	ED
		04	
	04	64	
		26	13
07	64	16	E1
	05	A4	91
	C3	AB	
		05	13
54		0C	C0
		E9	11
	FC4E	CF	9F
		9E	16
	0D	50	E9
	C3	AB	91
	01	A7	
		F4	12
	FF55		30

RPDCL
V04-000

- RESULT PARSE MAIN ROUTINE
GET OPTION VALUE

F 6

16-SEP-1984 00:13:01 VAX/VMS Macro V04-00
4-SEP-1984 23:42:58 [DCL.SRC]RPDCL.MAR;1

Page 27
(15)

FC06 30 0605 1151 BSBW
04 0608 1152 20\$: RET

QUALACT

; TAKE PROPER ACTION
; RETURN TO DISPATCHER


```
0609 1154 .SBTTL GET COMMAND LINE
0609 1155 :++
0609 1156 : FUNCTIONAL DESCRIPTION:
0609 1157 :
0609 1158 : THIS ROUTINE IS CALLED TO SET A DESCRIPTOR FOR THE COMMAND
0609 1159 : THAT WAS JUST PROCESSED BY DCL.
0609 1160 :
0609 1161 : CALLING SEQUENCE:
0609 1162 :
0609 1163 : THIS ROUTINE IS ENTERED BY A CASE FOLLOWING A CALL
0609 1164 :
0609 1165 : INPUT PARAMETERS:
0609 1166 :
0609 1167 : R9 = ADDRESS OF REQUEST DESCRIPTOR
0609 1168 : R11 = ADDRESS OF PASS 1 PARSE WORK AREA
0609 1169 :
0609 1170 : OUTPUT PARAMETERS:
0609 1171 :
0609 1172 : THE REQUEST DESCRIPTOR IS SET TO CONTAIN A QUADWORD DESCRIPTOR
0609 1173 : THE THE FINAL COMMAND IN THE BUFFER.
0609 1174 :
0609 1175 : IMPLICIT OUTPUTS:
0609 1176 :
0609 1177 : THE INTERNAL ERROR MECHANISM IS USED TO RETURN THE RESULTANT
0609 1178 : COMMAND LINE DESCRIPTOR WHEN COMMAND IS A RUN
0609 1179 :
0609 1180 : COMPLETION CODES:
0609 1181 :
0609 1182 : SUCCESS IN ALL CASES EXCEPT WHEN COMMAND IS A 'RUN'. IN THIS
0609 1183 : WAY, A UTILITY MAY DETERMIN THAT IS WAS INVOKED VIA A COMMAND,
0609 1184 : IE: LINK ALPHA, OR BY A 'RUN FILESPEC'.
0609 1185 :
0609 1186 :--
0609 1187 DCL$GETCMD::
0609 1188 BSBW DCL$GETDCLWRK ; GET COMMAND LINE
060C 1189 MOVW WRK_B_VERBTYP(R11),CLISB_RQSTAT(R9); SET WORK AREA POINTER
0611 1190 CLRL R5 ; GET VERB TYPE FOR CALLER
0613 1191 BSBW DCL$SETDESCADR ; START AT FIRST TOKEN
0616 1192 MOVL WRK_L_RSLEND(R11),R2 ; SET ADDRESS OF TOKEN DESCRIPTOR
061A 1193 EXTZV #PTR_V_OFFSET,#PTR_S_OFFSET,- ; GET ADDRESS OF NEXT FREE DESCRIPTOR
061D 1194 -PTR_C_LENGTH(R2),R2 ; GET OFFSET TO EOL
0620 1195 MOVW R2,R3 ; PRESET FIRST TOKEN TO EOL
0623 1196 10$: ADDL #PTR_C_LENGTH,R4 ; SKIP TO NEXT TOKEN
0626 1197 CMPZV #PTR_V_TYPE,#PTR_S_TYPE,(R4),#PTR_K_ENDLINE ; END OF LINE?
062B 1198 BEQL 20$ ; BRANCH IF DONE
062D 1199 CMPZV #PTR_V_OFFSET,#PTR_S_OFFSET,(R4),R3 ; FIRST TOKEN IN COMMAND?
0632 1200 BGEQU 10$ ; BRANCH IF NOT
0634 1201 EXTZV #PTR_V_OFFSET,#PTR_S_OFFSET,(R4),R3 ; SET OFFSET TO FIRST TOKEN
0639 1202 BRB 10$ ; PRECEEDS FIRST, SET IT AS NEW FIRST
063B 1203 20$: SUBL R3,R2 ; FIND LENGTH OF COMMAND
063E 1204 MOVAB WRK_G_BUFFER(R11)[R3],R3 ; GET ADDRESS OF FIRST TOKEN
0644 1205 CMPB #A"/",-1(R3) ; COMMAND TERMINATOR A SLASH?
0648 1206 BNEQ 30$ ; IF NOT-THEN DON'T INCLUE IT
064A 1207 INCL R2 ; ADD 1 TO COUNT
064C 1208 DECL R3 ; BACK UP ADDRESS TO TERMINATOR
064E 1209 30$: MOVQ R2,CLISQ_RQDESC(R9) ; SET RESULT IN CALLER DATA BLOCK
0652 1210 MOVL #1031,R0 ; SET INTERNAL ERROR BIT
```

03	A9	F9F4'	30	0609	1188	BSBW	DCL\$GETDCLWRK	; GET COMMAND LINE
		C2 AB	90	060C	1189	MOVW	WRK_B_VERBTYP(R11),CLISB_RQSTAT(R9);	SET WORK AREA POINTER
		55	D4	0611	1190	CLRL	R5	; GET VERB TYPE FOR CALLER
		F9EA'	30	0613	1191	BSBW	DCL\$SETDESCADR	; START AT FIRST TOKEN
52		B6 AB	D0	0616	1192	MOVL	WRK_L_RSLEND(R11),R2	; SET ADDRESS OF TOKEN DESCRIPTOR
		OC 08	EF	061A	1193	EXTZV	#PTR_V_OFFSET,#PTR_S_OFFSET,-	; GET ADDRESS OF NEXT FREE DESCRIPTOR
52		F4 A2		061D	1194		-PTR_C_LENGTH(R2),R2	; GET OFFSET TO EOL
		53 52	D0	0620	1195	MOVW	R2,R3	; PRESET FIRST TOKEN TO EOL
		54 OC	C0	0623	1196	ADDL	#PTR_C_LENGTH,R4	; SKIP TO NEXT TOKEN
04	64	04 1C	ED	0626	1197	CMPZV	#PTR_V_TYPE,#PTR_S_TYPE,(R4),#PTR_K_ENDLINE	; END OF LINE?
		OE	13	062B	1198	BEQL	20\$; BRANCH IF DONE
53	64	OC 08	ED	062D	1199	CMPZV	#PTR_V_OFFSET,#PTR_S_OFFSET,(R4),R3	; FIRST TOKEN IN COMMAND?
		EF 1E		0632	1200	BGEQU	10\$; BRANCH IF NOT
53	64	OC 08	EF	0634	1201	EXTZV	#PTR_V_OFFSET,#PTR_S_OFFSET,(R4),R3	; SET OFFSET TO FIRST TOKEN
		E8 11		0639	1202	BRB	10\$; PRECEEDS FIRST, SET IT AS NEW FIRST
		52 53	C2	063B	1203	SUBL	R3,R2	; FIND LENGTH OF COMMAND
53		F492 CB43	9E	063E	1204	MOVAB	WRK_G_BUFFER(R11)[R3],R3	; GET ADDRESS OF FIRST TOKEN
		FF A3 2F	91	0644	1205	CMPB	#A"/",-1(R3)	; COMMAND TERMINATOR A SLASH?
		04 12		0648	1206	BNEQ	30\$; IF NOT-THEN DON'T INCLUE IT
		52 D6		064A	1207	INCL	R2	; ADD 1 TO COUNT
		53 D7		064C	1208	DECL	R3	; BACK UP ADDRESS TO TERMINATOR
	08 A9	52 7D		064E	1209	MOVQ	R2,CLISQ_RQDESC(R9)	; SET RESULT IN CALLER DATA BLOCK
50	80000000	8F D0		0652	1210	MOVL	#1031,R0	; SET INTERNAL ERROR BIT

03	A9	24	91	0659	1211				
		07	13	065D	1212				
				065F	1213				
			04	0666	1214	90\$:			
				0667	1215				
				0667	1216				

CMPB	#CLISK_VERB_RUN,CLISB_RQSTAT(R9) :	WAS COMMAND A RUN?
BEQL	90\$: IF YES - THERE IS NO COMMAND LINE
STATUS	NORMAL	: SET GOOD STATUS
RET		: RETURN TO DISPATCHER
.END		

CALERR	00000040 R	02	CLIS_ABKEYW	= 00038010		
CALLBAK	0000022A R	02	CLIS_CONFQUAL	= 00038802		
CLISA_ABSACT	= 00000014		CLIS_ILLVAL	= 0003883A		
CLISA_ERRACT	= 00000004		CLIS_INVQUAL	= 0003880A		
CLISA_FLSACT	= 00000010		CLIS_INVREQTYP	= 00038822		
CLISA_PRSACT	= 00000010		CLIS_NOOPTPRS	= 00038842		
CLISA_QDVALADR	= 00000008		CLIS_NORMAL	= 00030001		
CLISA_QUALST	= 00000018		CLIS_NOVALUE	= 0003882A		
CLISA_TRUACT	= 0000000C		CLIS_REQPRMABS	= 00038812		
CLISB_BITNUM	= 00000001		CLIS_UNPROPARM	= 00038170		
CLISB_QDBLKSI2	= 00000000		CLIS_UNPROQUAL	= 00038168		
CLISB_QDCODE	= 00000001		CLIS_VALCNVERR	= 00038832		
CLISB_QDFLGS	= 00000002		CLINT	0000000BA R	02	
CLISB_QDSTAT	= 00000003		CMD_K_MAX_PARM	= 00000008		
CLISB_RQFLGS	= 00000002		CMPPRM	0000000CC R	02	
CLISB_RQSTAT	= 00000003		DCL\$CLRSETLST	000004C7 RG	02	
CLISB_RQTYPE	= 00000000		DCL\$CNVNOEDIT	***** X	02	
CLISC_QDBITS	= 00000014		DCL\$DCLPARSE	***** X	02	
CLISGET_PRC	***** X	02	DCL\$DISPATCH	***** X	02	
CLISK_CLINT	= 00000005		DCL\$ENDPARSE	***** X	02	
CLISK_CLISERV	= 00000005		DCL\$EXTNXTDESC	***** X	02	
CLISK_GETOPT	= 00000003		DCL\$EXTRSLDESC	***** X	02	
CLISK_GETQUAL	= 00000002		DCL\$FNDCMDQUAL	***** X	02	
CLISK_INITPRS	= 00000000		DCL\$GETCMD	00000609 RG	02	
CLISK_INPSPEC	= 00000001		DCL\$GETDCLWRK	***** X	02	
CLISK_NUMERVAL	= 00000040		DCL\$GETTEXTDESC	***** X	02	
CLISK_OUTSPEC	= 00000002		DCL\$GETLINE	***** X	02	
CLISK_PRESENT	= 00000050		DCL\$GETOPT	000005CC R	02	
CLISK_VERB_RUN	= 00000024		DCL\$GETPARM	***** X	02	
CLISL_RQVALU	= 0000000C		DCL\$GETPARMQUAL	***** X	02	
CLISM_CONCATINP	= 00000002		DCL\$GETQUALDESC	***** X	02	
CLISM_KEYVALU	= 00000002		DCL\$GETVALUE	***** X	02	
CLISM_MOREINP	= 00000004		DCL\$HANDLQUAL	0000055A RG	02	
CLISM_MOREVALS	= 00000001		DCL\$NEXTQUAL	***** X	02	
CLISM_PARMDEF	= 00000008		DCL\$PRESENT	***** X	02	
CLISM_PARMPRS	= 00000001		DCL\$PROCMDQUAL	0000050A RG	02	
CLISM_QUALEXP	= 00000002		DCL\$RPINIT	***** X	02	
CLISM_QUALTRU	= 00000001		DCL\$SETDEFVAL	000005B7 R	02	
CLISQ_QDVALDESC	= 00000004		DCL\$SETDESCADR	***** X	02	
CLISQ_RQDESC	= 00000008		DCL\$SETQUALVAL	00000580 R	02	
CLISS_PRITYP	= 00000004		DCL\$SETSETLST	000004BE RG	02	
CLISS_SUBTYP	= 00000004		DCL\$TSTSETLST	000004A4 RG	02	
CLISV_ABSADR	= 00000001		DCL\$UTLSERV	00000000 RG	02	
CLISV_ALLOCCUR	= 00000000		DCL\$VALCNV	000003E8 R	02	
CLISV_EXPNAME	= 00000002		ENT_V_BATDEF	= 00000003		
CLISV_LASTVAL	= 00000000		ENT_V_DEFTRUE	= 00000002		
CLISV_PARMPRS	= 00000000		ENT_W_DEFVAL	= 0000001C		
CLISV_PARMREQ	= 00000000		ENT_W_FLAGS	= 00000004		
CLISV_PRITYP	= 00000004		INPUT	00000398 R	02	
CLISV_QDEXPA	= 00000002		INTERIOR	= 0000001F		
CLISV_QDUSRV	= 00000001		OUTPUT	00000277 R	02	
CLISV_QUALEXP	= 00000001		PLM_B_FSTDDESC	00000001		
CLISV_QUALTRU	= 00000000		PLM_B_LSTDDESC	00000002		
CLISV_SUBTYP	= 00000000		PLM_B_NXTDESC	00000000		
CLISW_QDVALSI2	= 00000004		PLM_B_QUADESC	00000003		
CLISW_RQSIZE	= 00000008		PLM_B_TRMDESC	00000003		
CLISW_SERVCOD	= 00000001		PLM_C_SIZE	00000004		

PLM_K_SIZE	00000004
PRC_B_CONTINUE	000000F3
PRC_B_DEFRADIX	000000AE
PRC_B_EXMDEPMOD	000000AD
PRC_B_EXMDEPWID	000000AC
PRC_B_EXONLYL	0000012D
PRC_B_FLAGS2	000000AF
PRC_B_IMGFLAG	00000078
PRC_B_OUTFLAGS	0000012C
PRC_B_PROMPTLEN	000000F0
PRC_C_LENGTH	00000534
PRC_G_COMMANDS	00000133
PRC_G_PROMPT	000000F4
PRC_K_DEC	= 00000001
PRC_K_LENGTH	00000534
PRC_L_CURRKEY	00000048
PRC_L_EXMDEPADR	000000A8
PRC_L_EXTARG	00000094
PRC_L_EXTBLK	0000008C
PRC_L_EXTCOD	0000009C
PRC_L_EXTHND	00000090
PRC_L_EXTPRM	00000098
PRC_L_IDFLNK	000000BC
PRC_L_IMGACTSTS	00000080
PRC_L_INDCLOCK	0000007C
PRC_L_INDEPTH	0000005C
PRC_L_INDFAB	0000001C
PRC_L_INDINPRAB	00000014
PRC_L_INDOUTRAB	00000018
PRC_L_INPRAB	00000008
PRC_L_LASTKEY	0000004C
PRC_L_LSTSTATUS	000000B0
PRC_L_ONCTLY	000000B8
PRC_L_ONERROR	0000006C
PRC_L_OUTOFBAND	000000B4
PRC_L_OUTRAB	0000000C
PRC_L_OUTRABCTX	00000118
PRC_L_PPFLIST	00000070
PRC_L_RECALLPTR	0000012F
PRC_L_RESTART	00000058
PRC_L_SAVAP	00000000
PRC_L_SAVFP	00000004
PRC_L_SEVERITY	00000050
PRC_L_SPWN	000000C0
PRC_L_STACKLM	000000A4
PRC_L_STACKPT	000000A0
PRC_L_STATUS	00000054
PRC_L_STS	00000084
PRC_L_STV	00000088
PRC_L_SYMBOL	00000060
PRC_L_TMBX	00000074
PRC_L_TRMLIST	00000010
PRC_Q_ALLOCREG	00000020
PRC_Q_COMMAND	000000E0
PRC_Q_FLUSHTIME	000000D0
PRC_Q_GLOBAL	00000028
PRC_Q_IMAGENAME	000000D8

PRC_Q_KEYPAD	00000040
PRC_Q_LABEL	00000030
PRC_Q_LOCAL	00000038
PRC_Q_SAVEPRIV	000000E8
PRC_T_OUTDVI	0000011C
PRC_V_MODE	= 00000006
PRC_W_ASTIOSB	000000C6
PRC_W_ASTRETN	000000C8
PRC_W_ASTSTATUS	000000C4
PRC_W_ATTMBX	0000007A
PRC_W_FLAGS	00000068
PRC_W_INPCHAN	00000064
PRC_W_ONLEVEL	0000006A
PRC_W_OUTIFI	00000114
PRC_W_OUTISI	00000116
PRC_W_OUTMBXCHN	000000CA
PRC_W_OUTMBXREF	000000CE
PRC_W_OUTMBXSIZ	000000CC
PRC_W_PMPCTRL	000000F1
PRC_W_WAITIOSB	00000066
PROCIO	00000268
PTR_B_LEVEL	00000004
PTR_B_NUMBER	00000005
PTR_B_PARMCNT	00000006
PTR_B_VALUE	00000000
PTR_C_LENGTH	0000000C
PTR_K_BLANK	= 00000001
PTR_K_COLON	= 00000002
PTR_K_COMDQUAL	= 00000000
PTR_K_COMMA	= 00000005
PTR_K_ENDLINE	= 00000004
PTR_K_LENGTH	0000000C
PTR_K_LPAREN	= 00000007
PTR_K_PARAMETR	= 00000003
PTR_K_PARMQUAL	= 00000001
PTR_K_QUALVALU	= 00000002
PTR_L_DESCR	00000000
PTR_L_ENTITY	00000008
PTR_S_OFFSET	= 0000000C
PTR_S_TERM	= 00000004
PTR_S_TYPE	= 00000004
PTR_V_NEGATE	= 00000014
PTR_V_OFFSET	= 00000008
PTR_V_SYNTAX	= 00000016
PTR_V_TERM	= 00000018
PTR_V_TYPE	= 0000001C
QUACACT	0000020E
RET0	00000089
RET1	000003E7
RET2	000004A3
RPW_B_LSTDESC	00000009
RPW_B_STRPARM	00000008
RPW_C_HDRSIZ	00000040
RPW_C_LENGTH	00000080
RPW_G_BITS	00000020
RPW_G_PRMLIM	00000040
RPW_K_HDRSIZ	00000040

R 02

R R R 02
R 02
R 02

RPDCL
Symbol table

- RESULT PARSE MAIN ROUTINE

K 6

16-SEP-1984 00:13:01 VAX/VMS Macro V04-00
4-SEP-1984 23:42:58 [DCL.SRC]RPDCL.MAR;1

Page 32
(16)

RPW_K_LENGTH	00000080		
RPW_L_DCLWRK	00000004		
RPW_L_USERCTX	00000000		
RQBITS	= 0000000C		
RQDESC	= 00000004		
RQWORK	= 00000008		
RSBO	00000267	R	02
RSLTPRS	0000008A	R	02
SCANQUAL	00000244	R	02
SETQUAL	0000015A	R	02
WRK_B_CMDOPT	FFFFFFFFC3		
WRK_B_MAXPARM	FFFFFFFFD0		
WRK_B_MINPARM	FFFFFFFFD1		
WRK_B_PARMCNT	FFFFFFFFCE		
WRK_B_PARMSUM	FFFFFFFFCF		
WRK_B_RECALLCNT	FFFFFFFFC5		
WRK_B_VALLEV	FFFFFFFFC4		
WRK_B_VERBTYP	FFFFFFFFC2		
WRK_C_LENGTH	FFFFFF486		
WRK_G_BUFFER	FFFFFF492		
WRK_G_INPBUF	FFFFFF896		
WRK_G_RESULT	FFFFFF9B6		
WRK_K_LENGTH	FFFFFF486		
WRK_L_CHARPTR	FFFFFF48E		
WRK_L_DISALLOW	FFFFFFE6		
WRK_L_ERRORRTN	FFFFFF9AE		
WRK_L_EXPANDPTR	FFFFFF486		
WRK_L_IMAGE	FFFFFFE2		
WRK_L_MARKPTR	FFFFFF48A		
WRK_L_PAROUT	FFFFFFFD2		
WRK_L_PMPTADDR	FFFFFF9A2		
WRK_L_PROMPTRTN	FFFFFF9A6		
WRK_L_PROPTR	FFFFFFFC6		
WRK_L_QUABLK	FFFFFFCA		
WRK_L_READRTN	FFFFFF9AA		
WRK_L_RECALLPTR	FFFFFFEA		
WRK_L_RSLEND	FFFFFFB6		
WRK_L_RSLNXT	FFFFFFBA		
WRK_L_SAVAP	FFFFFFF8		
WRK_L_SAVFP	FFFFFFFC		
WRK_L_SAVSP	FFFFFFF4		
WRK_L_SIGNALRTN	FFFFFFD6		
WRK_L_SPECRTN	FFFFFF9B2		
WRK_L_TAB_VEC	FFFFFFDE		
WRK_L_VERB	FFFFFFBE		
WRK_W_FLAGS	FFFFFFF0		
WRK_W_FLAGS2	FFFFFFF2		
WRK_W_IMGCHAN	FFFFFFEE		
WRK_W_PMPTLEN	FFFFFF99E		
SS	= 00000055		

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes
ABS	00000000 (0.)	00 (0.)	NOPIC USR
\$ABSS	FFFFFFFFC (0.)	01 (1.)	NOPIC USR
DCL\$ZCODE	00000667 (1639.)	02 (2.)	NOPIC USR

	CON	ABS	LCL	NOSHR	NOEXE	NORD	NOWRT	NOVEC	BYTE
	CON	ABS	LCL	NOSHR	EXE	RD	WRT	NOVEC	BYTE
	CON	REL	LCL	NOSHR	EXE	RD	NOWRT	NOVEC	BYTE

+-----+
! Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	16	00:00:00.07	00:00:00.77
Command processing	97	00:00:00.63	00:00:07.33
Pass 1	310	00:00:12.67	00:00:43.11
Symbol table sort	0	00:00:01.56	00:00:04.85
Pass 2	217	00:00:03.33	00:00:12.84
Symbol table output	31	00:00:00.24	00:00:01.19
Psect synopsis output	2	00:00:00.02	00:00:00.03
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	673	00:00:18.54	00:01:10.12

The working set limit was 1650 pages.
68000 bytes (133 pages) of virtual memory were used to buffer the intermediate code.
There were 60 pages of symbol table space allocated to hold 914 non-local and 106 local symbols.
1216 source lines were read in Pass 1, producing 21 object records in Pass 2.
43 pages of virtual memory were used to define 29 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name	Macros defined
\$255\$DUA28:[SYSLIB]SYSBLDMLB.MLB;1	0
\$255\$DUA28:[DCL.OBJ]DCL.MLB;1	13
\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	2
\$255\$DUA28:[SYSLIB]STARLET.MLB;2	6
TOTALS (all libraries)	21

1079 GETS were required to define 21 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LISS:RPDCL/OBJ=OBJ\$:RPDCL MSRC\$:RPDCL/UPDATE=(ENH\$:RPDCL)+EXECMLS/LIB+LIB\$:DCL/LIB+SYSS\$LIBRARY:SYSBLDMLB/LIB

0073 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

